



SIMBA[®]
BY MAGNITUDE


Simba Impala ODBC Driver with SQL Connector

Installation and Configuration Guide

Simba Technologies Inc.

Version 2.6.11

June 30, 2020



Copyright © 2020 Magnitude Software, Inc. All rights reserved.

No part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, photocopying, recording, or otherwise, without prior written permission from Magnitude.

The information in this document is subject to change without notice. Magnitude strives to keep this information accurate but does not warrant that this document is error-free.

Any Magnitude product described herein is licensed exclusively subject to the conditions set forth in your Magnitude license agreement.

Simba, the Simba logo, SimbaEngine, and Simba Technologies are registered trademarks of Simba Technologies Inc. in Canada, the United States and/or other countries. All other trademarks and/or servicemarks are the property of their respective owners.

All other company and product names mentioned herein are used for identification purposes only and may be trademarks or registered trademarks of their respective owners.

Information about the third-party products is contained in a third-party-licenses.txt file that is packaged with the software.

Contact Us

Simba Technologies Inc.
938 West 8th Avenue
Vancouver, BC Canada
V5Z 1E5

Tel: +1 (604) 633-0008

Fax: +1 (604) 633-0004

www.simba.com

About This Guide

Purpose

The *Simba Impala ODBC Driver with SQL Connector Installation and Configuration Guide* explains how to install and configure the Simba Impala ODBC Driver with SQL Connector. The guide also provides details related to features of the driver.

Audience

The guide is intended for end users of the Simba Impala ODBC Driver, as well as administrators and developers integrating the driver.

Knowledge Prerequisites

To use the Simba Impala ODBC Driver, the following knowledge is helpful:

- Familiarity with the platform on which you are using the Simba Impala ODBC Driver
- Ability to use the data source to which the Simba Impala ODBC Driver is connecting
- An understanding of the role of ODBC technologies and driver managers in connecting to a data source
- Experience creating and configuring ODBC connections
- Exposure to SQL

Document Conventions

Italics are used when referring to book and document titles.

Bold is used in procedures for graphical user interface elements that a user clicks and text that a user types.

Monospace font indicates commands, source code, or contents of text files.

Note:

A text box with a pencil icon indicates a short note appended to a paragraph.

! Important:

A text box with an exclamation mark indicates an important comment related to the preceding paragraph.

Table of Contents

About the Simba Impala ODBC Driver	7
Windows Driver	8
Windows System Requirements	8
Installing the Driver on Windows	8
Creating a Data Source Name on Windows	9
Configuring Authentication on Windows	12
Configuring a Proxy Connection on Windows	17
Configuring HTTP Options on Windows	18
Configuring SSL Verification on Windows	18
Configuring Advanced Options on Windows	19
Configuring Server-Side Properties on Windows	21
Configuring Logging Options on Windows	22
Setting Driver-Wide Configuration Options on Windows	24
Configuring Kerberos Authentication for Windows	25
Verifying the Driver Version Number on Windows	30
macOS Driver	31
macOS System Requirements	31
Installing the Driver on macOS	31
Verifying the Driver Version Number on macOS	32
Linux Driver	33
Linux System Requirements	33
Installing the Driver Using the RPM File	34
Installing the Driver on Debian	35
Verifying the Driver Version Number on Linux	36
AIX Driver	37
AIX System Requirements	37
Installing the Driver on AIX	37
Verifying the Driver Version Number on AIX	38
Solaris Driver	39
Solaris System Requirements	39
Installing the Driver on Solaris	39
Verifying the Driver Version Number on Solaris	40

Configuring the ODBC Driver Manager on Non-Windows Machines	41
Specifying ODBC Driver Managers on Non-Windows Machines	41
Specifying the Locations of the Driver Configuration Files	42
Configuring ODBC Connections on a Non-Windows Machine	44
Creating a Data Source Name on a Non-Windows Machine	44
Configuring a DSN-less Connection on a Non-Windows Machine	47
Configuring Authentication on a Non-Windows Machine	49
Configuring SSL Verification on a Non-Windows Machine	53
Configuring Server-Side Properties on a Non-Windows Machine	54
Configuring Logging Options on a Non-Windows Machine	55
Setting Driver-Wide Configuration Options on a Non-Windows Machine	57
Testing the Connection on a Non-Windows Machine	58
Authentication Options	60
Using a Connection String	61
DSN Connection String Example	61
DSN-less Connection String Examples	61
Features	65
Data Types	65
Catalog and Schema Support	67
SQL Translation	67
Server-Side Properties	67
Active Directory	68
Write-back	68
Security and Authentication	68
Driver Configuration Options	70
Configuration Options Appearing in the User Interface	70
Configuration Options Having Only Key Names	95
Third-Party Trademarks	103

About the Simba Impala ODBC Driver

The Simba Impala ODBC Driver is used for direct SQL and Impala SQL access to Apache Hadoop / Impala distributions, enabling Business Intelligence (BI), analytics, and reporting on Hadoop / Impala-based data. The driver efficiently transforms an application's SQL query into the equivalent form in Impala SQL, which is a subset of SQL-92. If an application is Impala-aware, then the driver is configurable to pass the query through to the database for processing. The driver interrogates Impala to obtain schema information to present to a SQL-based application. Queries, including joins, are translated from SQL to Impala SQL. For more information about the differences between Impala SQL and SQL, see [Features](#) on page 65.

The Simba Impala ODBC Driver complies with the ODBC 3.80 data standard and adds important functionality such as Unicode and 32- and 64-bit support for high-performance computing environments.

ODBC is one of the most established and widely supported APIs for connecting to and working with databases. At the heart of the technology is the ODBC driver, which connects an application to the database. For more information about ODBC, see *Data Access Standards* on the Simba Technologies website: <https://www.simba.com/resources/data-access-standards-glossary>. For complete information about the ODBC specification, see the *ODBC API Reference* from the Microsoft documentation: <https://docs.microsoft.com/en-us/sql/odbc/reference/syntax/odbc-api-reference>.

The Simba Impala ODBC Driver is available for Microsoft® Windows®, Linux, Solaris, AIX, and macOS platforms.

The *Installation and Configuration Guide* is suitable for users who are looking to access data residing within Impala from their desktop environment. Application developers might also find the information helpful. Refer to your application for details on connecting via ODBC.

 **Note:**

For basic configuration instructions that allow you to quickly set up the Windows driver so that you can evaluate and use it, see the *Simba ODBC Drivers Quick Start Guide for Windows*. The Quick Start Guide also explains how to use the driver in various applications.


Windows Driver

Windows System Requirements

The Simba Impala ODBC Driver supports Apache Impala versions 2.8 through 3.3.

Install the driver on client machines where the application is installed. Before installing the driver, make sure that you have the following:

- Administrator rights on your machine.
- A machine that meets the following system requirements:
 - One of the following operating systems:
 - Windows 10, 8.1, or 7 SP1
 - Windows Server 2016, 2012, or 2008 R2 SP1
 - 100 MB of available disk space

 **Note:**

Support for Windows 7 SP1 and Windows Server 2008 R2 SP1 is deprecated, and will be removed in a future release of this driver. For more information, see the release notes.

Before the driver can be used, the Visual C++ Redistributable for Visual Studio 2013 with the same bitness as the driver must also be installed. If you obtained the driver from the Simba website, then your installation of the driver automatically includes this dependency. Otherwise, you must install the redistributable manually. You can download the installation packages for the redistributable at <https://www.microsoft.com/en-ca/download/details.aspx?id=40784>.

Installing the Driver on Windows

If you did not obtain this driver from the Simba website, you might need to follow a different installation procedure. For more information, see the *Simba OEM ODBC Drivers Installation Guide*.

On 64-bit Windows operating systems, you can execute both 32- and 64-bit applications. However, 64-bit applications must use 64-bit drivers, and 32-bit applications must use 32-bit drivers. Make sure that you use a driver whose bitness matches the bitness of the client application:

- `Simba Impala 2.6 32-bit.msi` for 32-bit applications
- `Simba Impala 2.6 64-bit.msi` for 64-bit applications

You can install both versions of the driver on the same machine.

To install the Simba Impala ODBC Driver on Windows:

1. Depending on the bitness of your client application, double-click to run **Simba Impala 2.6 32-bit.msi** or **Simba Impala 2.6 64-bit.msi**.
2. Click **Next**.
3. Select the check box to accept the terms of the License Agreement if you agree, and then click **Next**.
4. To change the installation location, click **Change**, then browse to the desired folder, and then click **OK**. To accept the installation location, click **Next**.
5. Click **Install**.
6. When the installation completes, click **Finish**.
7. If you received a license file through email, then copy the license file into the `\lib` subfolder of the installation folder you selected above. You must have Administrator privileges when changing the contents of this folder.

Creating a Data Source Name on Windows

Typically, after installing the Simba Impala ODBC Driver, you need to create a Data Source Name (DSN). A DSN is a data structure that stores connection information so that it can be used by the driver to connect to Impala.

Alternatively, you can specify connection settings in a connection string or as driver-wide settings. Settings in the connection string take precedence over settings in the DSN, and settings in the DSN take precedence over driver-wide settings.

The following instructions describe how to create a DSN. For information about specifying settings in a connection string, see [Using a Connection String](#) on page 61. For information about driver-wide settings, see [Setting Driver-Wide Configuration Options on Windows](#) on page 24.

To create a Data Source Name on Windows:

1. From the Start menu, go to **ODBC Data Sources**.

Note:

Make sure to select the ODBC Data Source Administrator that has the same bitness as the client application that you are using to connect to Impala.

2. In the ODBC Data Source Administrator, click the **Drivers** tab, and then scroll down as needed to confirm that the Simba Impala ODBC Driver appears in the alphabetical list of ODBC drivers that are installed on your system.
3. Choose one:
 - To create a DSN that only the user currently logged into Windows can use, click the **User DSN** tab.
 - Or, to create a DSN that all users who log into Windows can use, click the **System DSN** tab.

 **Note:**


It is recommended that you create a System DSN instead of a User DSN. Some applications load the data using a different user account, and might not be able to detect User DSNs that are created under another user account.

4. Click **Add**.
5. In the Create New Data Source dialog box, select **Simba Impala ODBC Driver** and then click **Finish**. The Simba Impala ODBC Driver DSN Setup dialog box opens.
6. In the **Data Source Name** field, type a name for your DSN.
7. Optionally, in the **Description** field, type relevant details about the DSN.
8. In the **Host** field, type the IP address or host name of the Impala server.
9. In the **Port** field, type the number of the TCP port that the Impala server uses to listen for client connections.

 **Note:**

The default port number used by Impala is 21050.

10. In the **Database** field, type the name of the database schema to use when a schema is not explicitly specified in a query.

 **Note:**

You can still issue queries on other schemas by explicitly specifying the schema in the query. To inspect your databases and determine the appropriate schema to use, type the `show databases` command at the Impala command prompt.

11. In the Authentication area, configure authentication as needed. For more information, see [Configuring Authentication on Windows](#) on page 12.

 **Note:**

The default configuration of Impala requires the Simba Impala ODBC Driver to be configured to use the No Authentication mechanism.

12. Optionally, if the operations against Impala are to be done on behalf of a user that is different than the authenticated user for the connection, type the name of the user to be delegated in the **Delegation UID** field.
13. In the **Transport Mode** drop-down list, select the Thrift transport protocol to use in the Thrift layer.

 **Note:**

For information about how to determine which Thrift transport protocols your Impala server supports, see [Authentication Options](#) on page 60.

14. To configure a connection through a proxy server, click **Proxy Options**. For more information, see [Configuring a Proxy Connection on Windows](#) on page 17.
15. If the Transport Mode option is set to HTTP, then to configure HTTP options such as custom headers, click **HTTP Options**. For more information, see [Configuring HTTP Options on Windows](#) on page 18.
16. To configure client-server verification over SSL, click **SSL Options**. For more information, see [Configuring SSL Verification on Windows](#) on page 18.
17. To configure advanced driver options, click **Advanced Options**. For more information, see [Configuring Advanced Options on Windows](#) on page 19.
18. To configure server-side properties, click **Advanced Options** and then click **Server Side Properties**. For more information, see [Configuring Server-Side Properties on Windows](#) on page 21.
19. To configure logging behavior for the driver, click **Logging Options**. For more information, see [Configuring Logging Options on Windows](#) on page 22.
20. To test the connection, click **Test**. Review the results as needed, and then click **OK**.

 **Note:**

If the connection fails, then confirm that the settings in the Simba Impala ODBC Driver DSN Setup dialog box are correct. Contact your Impala server administrator as needed.

21. To save your settings and close the Simba Impala ODBC Driver DSN Setup dialog box, click **OK**.
22. To close the ODBC Data Source Administrator, click **OK**.

Configuring Authentication on Windows

Some Impala servers are configured to require authentication for access. To connect to an Impala server, you must configure the Simba Impala ODBC Driver to use the authentication mechanism that matches the access requirements of the server and provides the necessary credentials.

For information about how to determine the type of authentication your Impala server requires, see [Authentication Options](#) on page 60.

You can specify authentication settings in a DSN, in a connection string, or as driver-wide settings. Settings in the connection string take precedence over settings in the DSN, and settings in the DSN take precedence over driver-wide settings.

The following authentication methods are available:

- [Using No Authentication](#) on page 12
- [Using Kerberos](#) on page 13
- [Using Advanced Kerberos](#) on page 14
- [Using SASL User Name](#) on page 16
- [Using User Name And Password](#) on page 16

If cookie-based authentication is enabled in your Impala database, you can specify a list of authentication cookies in the `HTTPAuthCookies` connection property. In this case, the driver authenticates the connection once based on the provided authentication credentials. It then uses the cookie generated by the server for each subsequent request in the same connection. For more information, see [HTTPAuthCookies](#) on page 98.

 **Note:**

On Windows, the `HTTPAuthCookies` property must be set in a connection string.

Using No Authentication

For this authentication mechanism, you do not need to configure any additional settings.

 **Note:**

The default configuration of Impala requires the Simba Impala ODBC Driver to be configured to use the No Authentication mechanism.

To configure a connection without authentication:

1. To access authentication options, open the ODBC Data Source Administrator where you created the DSN, then select the DSN, and then click **Configure**.
2. From the **Mechanism** drop-down list, select **No Authentication**.
3. If the Impala server is configured to use SSL, then click **SSL Options** to configure SSL for the connection. For more information, see [Configuring SSL Verification on Windows](#) on page 18.
4. To save your settings and close the dialog box, click **OK**.

Using Kerberos

If the Use Only SSPI advanced option is disabled, then Kerberos must be installed and configured before you can use this authentication mechanism. For information about configuring Kerberos on your machine, see [Configuring Kerberos Authentication for Windows](#) on page 25. For information about setting the Use Only SSPI advanced option, see [Configuring Advanced Options on Windows](#) on page 19.

To configure Kerberos authentication:

1. To access authentication options, open the ODBC Data Source Administrator where you created the DSN, then select the DSN, and then click **Configure**.
2. From the **Mechanism** drop-down list, select **Kerberos**.
3. Choose one:
 - To use the default realm defined in your Kerberos setup, leave the **Realm** field empty.
 - Or, if your Kerberos setup does not define a default realm or if the realm of your Impala server host is not the default, then, in the **Realm** field, type the Kerberos realm of the Impala server.
4. In the **Host FQDN** field, type the fully qualified domain name of the Impala server host.

 **Note:**

To use the Impala server host name as the fully qualified domain name for Kerberos authentication, in the **Host FQDN** field, type **_HOST**.

5. In the **Service Name** field, type the service name of the Impala server.
6. Optionally, if you are using MIT Kerberos and a Kerberos realm is specified in the **Realm** field, then choose one:
 - To have the Kerberos layer canonicalize the server's service principal name, leave the **Canonicalize Principal FQDN** check box selected.
 - Or, to prevent the Kerberos layer from canonicalizing the server's service principal name, clear the **Canonicalize Principal FQDN** check box.

7. To allow the driver to pass your credentials directly to the server for use in authentication, select **Delegate Kerberos Credentials**.
8. If the Impala server is configured to use SSL, then click **SSL Options** to configure SSL for the connection. For more information, see [Configuring SSL Verification on Windows](#) on page 18.
9. Optionally, in the **Transport Buffer Size** field, type the number of bytes to reserve in memory for buffering unencrypted data from the network.

 **Note:**

In most circumstances, the default value of 1000 bytes is optimal.

10. To save your settings and close the dialog box, click **OK**.

Using Advanced Kerberos

The Advanced Kerberos authentication mechanism allows concurrent connections within the same process to use different Kerberos user principals.

This authentication mechanism is supported only when the driver is configured to handle Kerberos authentication using MIT Kerberos:

- MIT Kerberos must be installed on your machine.
- The Use Only SSPI option must be disabled. For more information, see [Use Only SSPI](#) on page 92.

When you use Advanced Kerberos authentication, you do not need to run the `kinit` command to obtain a Kerberos ticket. Instead, you use a JSON file to map your Impala user name to a Kerberos user principal name and a keytab that contains the corresponding keys. The driver obtains Kerberos tickets based on the specified mapping. As a fallback, you can specify a keytab that the driver uses by default if the mapping file is not available or if no matching keytab can be found in the mapping file.


 **Note:**

- For information about the schema of the mapping file and how the driver handles invalid mappings, see [UPN Keytab Mapping File](#) on page 89.
- For information about how the driver searches for a keytab file if the keytab mapping and default keytab file are invalid, see [Default Keytab File](#) on page 75.

To configure Advanced Kerberos authentication:

1. To access authentication options, open the ODBC Data Source Administrator where you created the DSN, then select the DSN, and then click **Configure**.
2. In the **Mechanism** drop-down list, select **Kerberos**.

3. Choose one:
 - To use the default realm defined in your Kerberos setup, leave the **Realm** field empty.
 - Or, if your Kerberos setup does not define a default realm or if the realm of your Impala server host is not the default, then, in the **Realm** field, type the Kerberos realm of the Impala server.
4. In the **Host FQDN** field, type the fully qualified domain name of the Impala server host.

 **Note:**

To use the Impala server host name as the fully qualified domain name for Kerberos authentication, in the **Host FQDN** field, type **_HOST**.

5. In the **Service Name** field, type the service name of the Impala server.
6. Optionally, if you are using MIT Kerberos and a Kerberos realm is specified in the **Realm** field, then choose one:
 - To have the Kerberos layer canonicalize the server's service principal name, leave the **Canonicalize Principal FQDN** check box selected.
 - Or, to prevent the Kerberos layer from canonicalizing the server's service principal name, clear the **Canonicalize Principal FQDN** check box.
7. Select the **Use Keytab** check box.

 **Note:**

If the check box is not available, make sure that MIT Kerberos is installed on your machine.

8. In the **User Name** field, type an appropriate user name for accessing the Impala server.
9. Click **Keytab Options** and then do the following in the Keytab Options dialog box:
 - a. In the **UPN Keytab Mapping File** field, specify the full path to a JSON file that maps your Impala user name to a Kerberos user principal name and a keytab file.
 - b. In the **Default Keytab File** field, specify the full path to a keytab file that the driver can use if the mapping file is not available or if no matching keytab can be found in the mapping file.
 - c. To save your settings and close the dialog box, click **OK**.
10. If the Impala server is configured to use SSL, then click **SSL Options** to configure SSL for the connection. For more information, see [Configuring SSL Verification on Windows](#) on page 18.

11. Optionally, in the **Transport Buffer Size** field, type the number of bytes to reserve in memory for buffering unencrypted data from the network.

 **Note:**

In most circumstances, the default value of 1000 bytes is optimal.


12. To save your settings and close the dialog box, click **OK**.

Using SASL User Name

This authentication mechanism requires a user name but not a password. The user name labels the session, facilitating database tracking.

To configure SASL User Name authentication:

1. To access authentication options, open the ODBC Data Source Administrator where you created the DSN, then select the DSN, and then click **Configure**.
2. From the **Mechanism** drop-down list, select **SASL User Name**.
3. In the **User Name** field, type an appropriate user name for accessing the Impala server.
4. Optionally, in the **Transport Buffer Size** field, type the number of bytes to reserve in memory for buffering unencrypted data from the network.

 **Note:**

In most circumstances, the default value of 1000 bytes is optimal.

5. To save your settings and close the dialog box, click **OK**.

Using User Name And Password

This authentication mechanism requires a user name and a password.

 **Note:**

This authentication mechanism should not be used with an Impala configuration that does not have LDAP enabled.

To configure User Name And Password authentication:

1. To access authentication options, open the ODBC Data Source Administrator where you created the DSN, then select the DSN, and then click **Configure**.
2. From the **Mechanism** drop-down list, select **User Name And Password**.
3. In the **User Name** field, type an appropriate user name for accessing the Impala server.

4. In the **Password** field, type the password corresponding to the user name you typed above.
5. To save the password, select the **Save Password (Encrypted)** check box.

! Important:

The password is obscured, that is, not saved in plain text. However, it is still possible for the encrypted password to be copied and used.

6. If the Impala server is configured to use SSL, then click **SSL Options** to configure SSL for the connection. For more information, see [Configuring SSL Verification on Windows](#) on page 18.
7. Optionally, in the **Transport Buffer Size** field, type the number of bytes to reserve in memory for buffering unencrypted data from the network.

 **Note:**

In most circumstances, the default value of 1000 bytes is optimal.

8. Optionally, to use SASL to handle authentication, select the **Use Simple Authentication and Security Layer (SASL)** check box.

 **Note:**

If the Transport Mode property is specified, it takes precedence over this property.

9. To save your settings and close the dialog box, click **OK**.

Configuring a Proxy Connection on Windows

If you are connecting to the data source through a proxy server, you must provide connection information for the proxy server.

To configure a proxy server connection on Windows:

1. To access proxy server options, open the ODBC Data Source Administrator where you created the DSN, then select the DSN, then click **Configure**, and then click **Proxy Options**.
2. Select the **Use Proxy** check box.
3. In the **Proxy Host** field, type the host name or IP address of the proxy server.
4. In the **Proxy Port** field, type the number of the TCP port that the proxy server uses to listen for client connections.
5. In the **Proxy Username** field, type your user name for accessing the proxy server.

6. In the **Proxy Password** field, type the password corresponding to the user name.
7. To encrypt your credentials, select one of the following:
 - If the credentials are used only by the current Windows user, select **Current User Only**.
 - Or, if the credentials are used by all users on the current Windows machine, select **All Users Of This Machine**.
8. To save your settings and close the HTTP Proxy Options dialog box, click **OK**.

Configuring HTTP Options on Windows

You can configure options such as custom headers when using the HTTP transport protocol in the Thrift layer. For information about how to determine if your Impala server supports the HTTP transport protocol, see [Authentication Options](#) on page 60.

The following instructions describe how to configure HTTP options in a DSN. You can specify the connection settings described below in a DSN, in a connection string, or as driver-wide settings. Settings in the connection string take precedence over settings in the DSN, and settings in the DSN take precedence over driver-wide settings.

To configure HTTP options on Windows:

1. Open the ODBC Data Source Administrator where you created the DSN, then select the DSN, then click **Configure**, and then make sure that the Transport Mode option is set to **HTTP**.
2. To access HTTP options, click **HTTP Options**.

 **Note:**

The HTTP options are available only when the Transport Mode option is set to HTTP.

3. In the **HTTP Path** field, type the partial URL corresponding to the Impala server.
4. To create a custom HTTP header, click **Add**, then type appropriate values in the **Key** and **Value** fields, and then click **OK**.
5. To edit a custom HTTP header, select the header from the list, then click **Edit**, then update the **Key** and **Value** fields as needed, and then click **OK**.
6. To delete a custom HTTP header, select the header from the list, and then click **Remove**. In the confirmation dialog box, click **Yes**.
7. To save your settings and close the HTTP Properties dialog box, click **OK**.

Configuring SSL Verification on Windows

If you are connecting to an Impala server that has Secure Sockets Layer (SSL) enabled, you can configure the driver to connect to an SSL-enabled socket. When

using SSL to connect to a server, the driver can be configured to verify the identity of the server.

The following instructions describe how to configure SSL in a DSN. You can specify the connection settings described below in a DSN, in a connection string, or as driver-wide settings. Settings in the connection string take precedence over settings in the DSN, and settings in the DSN take precedence over driver-wide settings.

To configure SSL verification on Windows:

1. To access SSL options, open the ODBC Data Source Administrator where you created the DSN, then select the DSN, then click **Configure**, and then click **SSL Options**.
2. Select the **Enable SSL** check box.
3. To allow authentication using self-signed certificates that have not been added to the list of trusted certificates, select the **Allow Self-signed Server Certificate** check box.
4. To allow the common name of a CA-issued SSL certificate to not match the host name of the Impala server, select the **Allow Common Name Host Name Mismatch** check box.
5. To specify the CA certificates that you want to use to verify the server, do one of the following:
 - To verify the server using the trusted CA certificates from a specific `.pem` file, specify the full path to the file in the **Trusted Certificates** field and clear the **Use System Trust Store** check box.
 - Or, to use the trusted CA certificates `.pem` file that is installed with the driver, leave the **Trusted Certificates** field empty, and clear the **Use System Trust Store** check box.
 - Or, to use the Windows trust store, select the **Use System Trust Store** check box.
6. From the **Minimum TLS Version** drop-down list, select the minimum version of TLS to use when connecting to your data store.
7. To save your settings and close the SSL Options dialog box, click **OK**.

! Important:

- If you are using the Windows trust store, make sure to import the trusted CA certificates into the trust store.
- If the trusted CA supports certificate revocation, select the **Check Certificate Revocation** check box.

Configuring Advanced Options on Windows

You can configure advanced options to modify the behavior of the driver.

The following instructions describe how to configure advanced options in a DSN. You can specify the connection settings described below in a DSN, in a connection string, or as driver-wide settings. Settings in the connection string take precedence over settings in the DSN, and settings in the DSN take precedence over driver-wide settings.

To configure advanced options on Windows:

1. To access advanced options, open the ODBC Data Source Administrator where you created the DSN, then select the DSN, then click **Configure**, and then click **Advanced Options**.
2. To disable translation from ODBC SQL to Impala SQL, select the **Use Native Query** check box.

! Important:

- When this option is enabled, the driver cannot execute parameterized queries.
- By default, the driver applies transformations to the queries emitted by an application to convert the queries into an equivalent form in Impala SQL. If the application is Impala-aware and already emits Impala SQL, then turning off the translation avoids the additional overhead of query transformation.

3. To enable the driver to successfully run queries that contain transaction statements, select the **Ignore Transactions** check box.

Note:

The transaction statements are not executed, because ODBC does not support them. Enabling this option allows the driver to run the query without returning error messages.

4. To enable the driver to return SQL_WVARCHAR instead of SQL_VARCHAR for STRING and VARCHAR columns, and SQL_WCHAR instead of SQL_CHAR for CHAR columns, select the **Use SQL Unicode Types** check box.
5. To have the driver automatically attempt to reconnect to the server if communications are lost, select **Enable Auto Reconnect**.
6. To have the driver restrict catalog queries to the current schema when no schema is specified, or when the schema is specified with the wildcard character %, select **Restrict Metadata with Current Schema**.
7. In the **Rows Fetched Per Block** field, type the number of rows to be fetched per block.
8. In the **Socket Timeout** field, type the number of seconds that the TCP socket waits for a response from the server before timing out the request and returning an error message.

 **Note:**

Setting the Socket Timeout value to 0 disables the timeout feature.

9. In the **String Column Length** field, type the maximum data length for STRING columns.
10. In the **Async Exec Poll Interval** field, type the time in milliseconds between each poll for the query execution status.
11. To handle Kerberos authentication using the SSPI plugin instead of MIT Kerberos by default, select one or both of the check boxes under the **Use Only SSPI** option:
 - To configure the current DSN to use the SSPI plugin by default, select **Enable For This DSN**.
 - To configure all DSN-less connections to use the SSPI plugin by default, select **Enable For DSN-less Connections**.
 - To configure all connections that use the Simba Impala ODBC Driver to use the SSPI plugin by default, select both check boxes.
12. Optionally, if you want the driver to retry queries that fail, select the **Enable Query Retry** check box and then do the following:
 - a. In the **Max Retries** field, type the maximum number of times that the driver retries each query.
 - b. In the **Result Set Cache Size** field, type the maximum amount of memory that the result set cache can occupy. Values must be specified in: B (bytes), KB (kilobytes), MB (megabytes), or GB (gigabytes).
 - c. In the **Retry Interval** field, type the amount of time that the driver waits between query retry attempts. Values must be specified in S (seconds) or MS (milliseconds).
13. To save your settings and close the Advanced Options dialog box, click **OK**.

Configuring Server-Side Properties on Windows

When connecting to a server that is running Impala 2.0 or later, you can use the driver to apply configuration properties to the server.

 **Important:**

This feature is not supported for earlier versions of Impala, where the SET statement can only be executed from within the Impala shell.

The following instructions describe how to configure server-side properties in a DSN. You can specify the connection settings described below in a DSN, in a connection string, or as driver-wide settings. Settings in the connection string take precedence

over settings in the DSN, and settings in the DSN take precedence over driver-wide settings.

To configure server-side properties on Windows:

1. To configure server-side properties, open the ODBC Data Source Administrator where you created the DSN, then select the DSN, then click **Configure**, then click **Advanced Options**, and then click **Server Side Properties**.
2. To create a server-side property, click **Add**, then type appropriate values in the **Key** and **Value** fields, and then click **OK**. For example, to set the value of the MEM_LIMIT query option to 1 GB, type **MEM_LIMIT** in the **Key** field and then type **1000000000** in the **Value** field.
3. To edit a server-side property, select the property from the list, then click **Edit**, then update the **Key** and **Value** fields as needed, and then click **OK**.
4. To delete a server-side property, select the property from the list, and then click **Remove**. In the confirmation dialog box, click **Yes**.
5. To configure the driver to convert server-side property key names to all lower-case characters, select the **Convert Key Name To Lower Case** check box.
6. To save your settings and close the Server Side Properties dialog box, click **OK**.

Configuring Logging Options on Windows

To help troubleshoot issues, you can enable logging. In addition to functionality provided in the Simba Impala ODBC Driver, the ODBC Data Source Administrator provides tracing functionality.

! Important:

Only enable logging or tracing long enough to capture an issue. Logging or tracing decreases performance and can consume a large quantity of disk space.


The settings for logging apply to every connection that uses the Simba Impala ODBC Driver, so make sure to disable the feature after you are done using it.

To enable driver logging on Windows:

1. To access logging options, open the ODBC Data Source Administrator where you created the DSN, then select the DSN, then click **Configure**, and then click **Logging Options**.
2. From the **Log Level** drop-down list, select the logging level corresponding to the amount of information that you want to include in log files:

Logging Level	Description
OFF	Disables all logging.
FATAL	Logs severe error events that lead the driver to abort.
ERROR	Logs error events that might allow the driver to continue running.
WARNING	Logs events that might result in an error if action is not taken.
INFO	Logs general information that describes the progress of the driver.
DEBUG	Logs detailed information that is useful for debugging the driver.
TRACE	Logs all driver activity.

3. In the **Log Path** field, specify the full path to the folder where you want to save log files.
4. If requested by Technical Support, type the name of the component for which to log messages in the **Log Namespace** field. Otherwise, do not type a value in the field.
5. In the **Max Number Files** field, type the maximum number of log files to keep.

 **Note:**

After the maximum number of log files is reached, each time an additional file is created, the driver deletes the oldest log file.

6. In the **Max File Size** field, type the maximum size of each log file in megabytes (MB).

 **Note:**

After the maximum file size is reached, the driver creates a new file and continues logging.

7. Click **OK**.
8. Restart your ODBC application to make sure that the new settings take effect.

The Simba Impala ODBC Driver produces the following log files at the location you specify in the Log Path field:

- A `simbaimpalaodbcdriver.log` file that logs driver activity that is not specific to a connection.
- A `simbaimpalaodbcdriver_connection_[Number].log` file for each connection made to the database, where *[Number]* is a number that identifies each log file. This file logs driver activity that is specific to the connection.

If you enable the `UseLogPrefix` connection property, the driver prefixes the log file name with the user name associated with the connection and the process ID of the application through which the connection is made. For more information, see [UseLogPrefix](#) on page 101.

To disable driver logging on Windows:

1. Open the ODBC Data Source Administrator where you created the DSN, then select the DSN, then click **Configure**, and then click **Logging Options**.
2. From the **Log Level** drop-down list, select **LOG_OFF**.
3. Click **OK**.
4. Restart your ODBC application to make sure that the new settings take effect.


Setting Driver-Wide Configuration Options on Windows

When you specify connection settings in a DSN or connection string, those settings apply only when you connect to Impala using that particular DSN or string. As an alternative, you can specify settings that apply to every connection that uses the Simba Impala ODBC Driver by configuring them in the Windows Registry.

Note:

Settings in the connection string take precedence over settings in the DSN, and settings in the DSN take precedence over driver-wide settings.

To set driver-wide configuration options on Windows:

1. Choose one:
 - If you are using Windows 7 or earlier, click **Start** , then type **regedit** in the **Search** field, and then click **regedit.exe** in the search results.
 - Or, if you are using Windows 8 or later, on the Start screen, type **regedit**, and then click the **regedit** search result.
2. Navigate to the appropriate registry key for the bitness of your driver and your machine:
 - If you are using the 32-bit driver on a 64-bit machine, then browse to the following registry key:

HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Simba\Simba Impala ODBC Driver\Driver

- Otherwise, browse to the following registry key:

HKEY_LOCAL_MACHINE\SOFTWARE\Simba\Simba Impala ODBC Driver\Driver

3. For each connection property that you want to configure, do the following:
 - a. Right-click the **Driver** subkey and then select **New > String Value**.
 - b. Type the key name of the connection property, and then press **Enter**.

For example, to specify the authentication mechanism to use, type `AuthMech`. To verify the supported key name for each driver configuration option, refer to the "Key Name" column in the description of the option in [Driver Configuration Options](#) on page 70.

- c. Right-click the value that you created in the previous steps and then click **Modify**.
- d. In the Edit String dialog box, in the **Value Data** field, type the value that you want to set the connection property to and then click **OK**.

For example, to specify the Kerberos authentication mechanism, type 1.

4. Close the Registry Editor.

Configuring Kerberos Authentication for Windows

Active Directory

The Simba Impala ODBC Driver supports Active Directory Kerberos on Windows. There are two prerequisites for using Active Directory Kerberos on Windows:

- MIT Kerberos is not installed on the client Windows machine.
- The MIT Kerberos Hadoop realm has been configured to trust the Active Directory realm, according to Apache's documentation, so that users in the Active Directory realm can access services in the MIT Kerberos Hadoop realm.

MIT Kerberos

Downloading and Installing MIT Kerberos for Windows 4.0.1

For information about Kerberos and download links for the installer, see the MIT Kerberos website: <http://web.mit.edu/kerberos/>.

To download and install MIT Kerberos for Windows 4.0.1:

1. Download the appropriate Kerberos installer:
 - For a 64-bit machine, use the following download link from the MIT Kerberos website: <http://web.mit.edu/kerberos/dist/kfw/4.0/kfw-4.0.1-amd64.msi>.
 - For a 32-bit machine, use the following download link from the MIT Kerberos website: <http://web.mit.edu/kerberos/dist/kfw/4.0/kfw-4.0.1-i386.msi>.

 **Note:**

The 64-bit installer includes both 32-bit and 64-bit libraries. The 32-bit installer includes 32-bit libraries only.

2. To run the installer, double-click the `.msi` file that you downloaded above.
3. Follow the instructions in the installer to complete the installation process.
4. When the installation completes, click **Finish**.

Setting Up the Kerberos Configuration File

Settings for Kerberos are specified through a configuration file. You can set up the configuration file as an `.ini` file in the default location, which is the `C:\ProgramData\MIT\Kerberos5` directory, or as a `.conf` file in a custom location.

Normally, the `C:\ProgramData\MIT\Kerberos5` directory is hidden. For information about viewing and using this hidden directory, refer to Microsoft Windows documentation.


 **Note:**

For more information on configuring Kerberos, refer to the MIT Kerberos documentation.

To set up the Kerberos configuration file in the default location:

1. Obtain a `krb5.conf` configuration file. You can obtain this file from your Kerberos administrator, or from the `/etc/krb5.conf` folder on the machine that is hosting the Impala server.
2. Rename the configuration file from `krb5.conf` to `krb5.ini`.
3. Copy the `krb5.ini` file to the `C:\ProgramData\MIT\Kerberos5` directory and overwrite the empty sample file.


To set up the Kerberos configuration file in a custom location:

1. Obtain a `krb5.conf` configuration file. You can obtain this file from your Kerberos administrator, or from the `/etc/krb5.conf` folder on the machine that is hosting the Impala server.
2. Place the `krb5.conf` file in an accessible directory and make note of the full path name.
3. Open the System window:
 - If you are using Windows 7 or earlier, click **Start** , then right-click **Computer**, and then click **Properties**.
 - Or, if you are using Windows 8 or later, right-click **This PC** on the Start screen, and then click **Properties**.
4. Click **Advanced System Settings**.
5. In the System Properties dialog box, click the **Advanced** tab and then click **Environment Variables**.
6. In the Environment Variables dialog box, under the System Variables list, click **New**.
7. In the New System Variable dialog box, in the **Variable Name** field, type **KRB5_CONFIG**.
8. In the **Variable Value** field, type the full path to the `krb5.conf` file.
9. Click **OK** to save the new variable.
10. Make sure that the variable is listed in the System Variables list.
11. Click **OK** to close the Environment Variables dialog box, and then click **OK** to close the System Properties dialog box.

Setting Up the Kerberos Credential Cache File

Kerberos uses a credential cache to store and manage credentials.

To set up the Kerberos credential cache file:

1. Create a directory where you want to save the Kerberos credential cache file. For example, create a directory named `C:\temp`.
2. Open the System window:
 - If you are using Windows 7 or earlier, click **Start** , then right-click **Computer**, and then click **Properties**.
 - Or, if you are using Windows 8 or later, right-click **This PC** on the Start screen, and then click **Properties**.
3. Click **Advanced System Settings**.
4. In the System Properties dialog box, click the **Advanced** tab and then click **Environment Variables**.

5. In the Environment Variables dialog box, under the System Variables list, click **New**.
6. In the New System Variable dialog box, in the **Variable Name** field, type **KRB5CCNAME**.
7. In the **Variable Value** field, type the path to the folder you created above, and then append the file name `krb5cache`. For example, if you created the folder `C:\temp`, then type `C:\temp\krb5cache`.

 **Note:**

`krb5cache` is a file (not a directory) that is managed by the Kerberos software, and it should not be created by the user. If you receive a permission error when you first use Kerberos, make sure that the `krb5cache` file does not already exist as a file or a directory.

8. Click **OK** to save the new variable.
9. Make sure that the variable appears in the System Variables list.
10. Click **OK** to close the Environment Variables dialog box, and then click **OK** to close the System Properties dialog box.
11. To make sure that Kerberos uses the new settings, restart your machine.

Obtaining a Ticket for a Kerberos Principal


A principal refers to a user or service that can authenticate to Kerberos. To authenticate to Kerberos, a principal must obtain a ticket by using a password or a keytab file. You can specify a keytab file to use, or use the default keytab file of your Kerberos configuration.

To obtain a ticket for a Kerberos principal using a password:

1. Open MIT Kerberos Ticket Manager.
2. In MIT Kerberos Ticket Manager, click **Get Ticket**.
3. In the Get Ticket dialog box, type your principal name and password, and then click **OK**.

If the authentication succeeds, then your ticket information appears in MIT Kerberos Ticket Manager.

To obtain a ticket for a Kerberos principal using a keytab file:

1. Open a command prompt:
 - If you are using Windows 7 or earlier, click **Start** , then click **All Programs**, then click **Accessories**, and then click **Command Prompt**.

- If you are using Windows 8 or later, click the arrow button at the bottom of the Start screen, then find the Windows System program group, and then click **Command Prompt**.
2. In the Command Prompt, type a command using the following syntax:

```
kinit -k -t [KeytabPath][Principal]
```

[KeytabPath] is the full path to the keytab file. For example:

C:\mykeytabs\myUser.keytab.

[Principal] is the Kerberos user principal to use for authentication. For example:

myUser@EXAMPLE.COM.

3. If the cache location KRB5CCNAME is not set or used, then use the `-c` option of the `kinit` command to specify the location of the credential cache. In the command, the `-c` argument must appear last. For example:


```
kinit -k -t C:\mykeytabs\myUser.keytab  
myUser@EXAMPLE.COM -c C:\ProgramData\MIT\krbcache
```

Krbcache is the Kerberos cache file, not a directory.

To obtain a ticket for a Kerberos principal using the default keytab file:

Note:

For information about configuring a default keytab file for your Kerberos configuration, refer to the MIT Kerberos documentation.

1. Open a command prompt:
 - If you are using Windows 7 or earlier, click **Start** , then click **All Programs**, then click **Accessories**, and then click **Command Prompt**.
 - If you are using Windows 8 or later, click the arrow button at the bottom of the Start screen, then find the Windows System program group, and then click **Command Prompt**.
2. In the Command Prompt, type a command using the following syntax:

```
kinit -k [principal]
```

[principal] is the Kerberos user principal to use for authentication. For example:

MyUser@EXAMPLE.COM.

3. If the cache location KRB5CCNAME is not set or used, then use the `-c` option of the `kinit` command to specify the location of the credential cache. In the command, the `-c` argument must appear last. For example:

```
kinit -k -t C:\mykeytabs\myUser.keytab  
myUser@EXAMPLE.COM -c C:\ProgramData\MIT\krbcache
```


Krbcache is the Kerberos cache file, not a directory.

Verifying the Driver Version Number on Windows

If you need to verify the version of the Simba Impala ODBC Driver that is installed on your Windows machine, you can find the version number in the ODBC Data Source Administrator.

To verify the driver version number on Windows:

1. From the Start menu, go to **ODBC Data Sources**.

 **Note:**

Make sure to select the ODBC Data Source Administrator that has the same bitness as the client application that you are using to connect to Impala.

2. Click the **Drivers** tab and then find the Simba Impala ODBC Driver in the list of ODBC drivers that are installed on your system. The version number is displayed in the **Version** column.

macOS Driver

macOS System Requirements

The Simba Impala ODBC Driver supports Apache Impala versions 2.8 through 3.3.

Install the driver on client machines where the application is installed. Each client machine that you install the driver on must meet the following minimum system requirements:

- macOS version 10.13 or 10.14
- 100MB of available disk space
- One of the following ODBC driver managers installed:
 - iODBC 3.52.9 or later
 - unixODBC 2.2.14 or later


Installing the Driver on macOS

If you did not obtain this driver from the Simba website, you might need to follow a different installation procedure. For more information, see the *Simba OEM ODBC Drivers Installation Guide*.

The Simba Impala ODBC Driver is available for macOS as a .dmg file named `Simba Impala 2.6.dmg`. The driver supports both 32- and 64-bit client applications.

To install the Simba Impala ODBC Driver on macOS:

1. Double-click **Simba Impala 2.6.dmg** to mount the disk image.
2. Double-click **Simba Impala 2.6.pkg** to run the installer.
3. In the installer, click **Continue**.
4. On the Software License Agreement screen, click **Continue**, and when the prompt appears, click **Agree** if you agree to the terms of the License Agreement.
5. Optionally, to change the installation location, click **Change Install Location**, then select the desired location, and then click **Continue**.

 **Note:**

By default, the driver files are installed in the `/Library/simba/impala` directory.

6. To accept the installation location and begin the installation, click **Install**.
7. When the installation completes, click **Close**.

8. If you received a license file through email, then copy the license file into the `/lib` subfolder in the driver installation directory. You must have root privileges when changing the contents of this folder.

For example, if you installed the driver to the default location, you would copy the license file into the `/Library/simba/impala/lib` folder.

Next, configure the environment variables on your machine to make sure that the ODBC driver manager can work with the driver. For more information, see [Configuring the ODBC Driver Manager on Non-Windows Machines](#) on page 41.

Verifying the Driver Version Number on macOS

If you need to verify the version of the Simba Impala ODBC Driver that is installed on your macOS machine, you can query the version number through the Terminal.

To verify the driver version number on macOS:

- At the Terminal, run the following command:

```
pkgutil --info simba.impalaodbc
```

The command returns information about the Simba Impala ODBC Driver that is installed on your machine, including the version number.

Linux Driver

For most Linux distributions, you can install the driver using the RPM file. If you are installing the driver on a Debian machine, you must use the Debian package.

Linux System Requirements

The Simba Impala ODBC Driver supports Apache Impala versions 2.8 through 3.3.

Install the driver on client machines where the application is installed. Each client machine that you install the driver on must meet the following minimum system requirements:

- One of the following distributions:
 - Red Hat® Enterprise Linux® (RHEL) 6 or 7
 - CentOS 6 or 7
 - SUSE Linux Enterprise Server (SLES) 11 or 12
 - Debian 8 or 9
 - Ubuntu 14.04, 16.04, or 18.04
 - Oracle Linux 7.5 or 7.6

 **Note:**

Support for CentOS 6 and RHEL 6 is deprecated, and will be removed in a future release of this driver. For more information, see the release notes.

- 50 MB of available disk space
- One of the following ODBC driver managers installed:
 - iODBC 3.52.9 or later
 - unixODBC 2.2.14 or later
- All of the following `libsasl` libraries installed:
 - `cyrus-sasl-2.1.22-7` or later
 - `cyrus-sasl-gssapi-2.1.22-7` or later
 - `cyrus-sasl-plain-2.1.22-7` or later

 **Note:**

If the package manager in your Linux distribution cannot resolve the dependencies automatically when installing the driver, then download and manually install the packages.

To install the driver, you must have root access on the machine.

Installing the Driver Using the RPM File

If you did not obtain this driver from the Simba website, you might need to follow a different installation procedure. For more information, see the *Simba OEM ODBC Drivers Installation Guide*.

On 64-bit editions of Linux, you can execute both 32- and 64-bit applications. However, 64-bit applications must use 64-bit drivers, and 32-bit applications must use 32-bit drivers. Make sure that you use a driver whose bitness matches the bitness of the client application:

- `simbaimpala-[Version]-[Release].i686.rpm` for the 32-bit driver
- `simbaimpala-[Version]-[Release].x86_64.rpm` for the 64-bit driver

The placeholders in the file names are defined as follows:

- *[Version]* is the version number of the driver.
- *[Release]* is the release number for this version of the driver.

You can install both the 32-bit and 64-bit versions of the driver on the same machine.

To install the Simba Impala ODBC Driver using the RPM File:

1. Log in as the root user.
2. Navigate to the folder containing the RPM package for the driver.
3. Depending on the Linux distribution that you are using, run one of the following commands from the command line, where *[RPMFileName]* is the file name of the RPM package:

- If you are using Red Hat Enterprise Linux or CentOS, run the following command:

```
yum --nogpgcheck localinstall [RPMFileName]
```

- Or, if you are using SUSE Linux Enterprise Server, run the following command:

```
zypper install [RPMFileName]
```

The Simba Impala ODBC Driver files are installed in the `/opt/simba/impala` directory.

Note:

If the package manager in your Linux distribution cannot resolve the `libsasl` dependencies automatically when installing the driver, then download and manually install the packages.

4. If you received a license file through email, then copy the license file into the `/opt/simba/impala/lib/32` or `/opt/simba/impala/lib/64` folder, depending on the version of the driver that you installed.

Next, configure the environment variables on your machine to make sure that the ODBC driver manager can work with the driver. For more information, see [Configuring the ODBC Driver Manager on Non-Windows Machines](#) on page 41.

Installing the Driver on Debian

To install the driver on a Debian machine, use the Debian package instead of the RPM file or tarball package.

On 64-bit editions of Debian, you can execute both 32- and 64-bit applications. However, 64-bit applications must use 64-bit drivers, and 32-bit applications must use 32-bit drivers. Make sure that you use the version of the driver that matches the bitness of the client application:

- `simbaimpala_[Version]-[Release]_i386.deb` for the 32-bit driver
- `simbaimpala_[Version]-[Release]_amd64.deb` for the 64-bit driver

[Version] is the version number of the driver, and *[Release]* is the release number for this version of the driver.

You can install both versions of the driver on the same machine.

To install the Simba Impala ODBC Driver on Debian:

1. Log in as the root user, and then navigate to the folder containing the Debian package for the driver.
2. Double-click `simbaimpala_[Version]-[Release]_i386.deb` or `simbaimpala_[Version]-[Release]_amd64.deb`.
3. Follow the instructions in the installer to complete the installation process.

The Simba Impala ODBC Driver files are installed in the `/opt/simba/impala` directory.

Note:

If the package manager in your Ubuntu distribution cannot resolve the `libsasl` dependencies automatically when installing the driver, then download and manually install the packages required by the version of the driver that you want to install.

4. If you received a license file via email, then copy the license file into the `/opt/simba/impala/lib/32` or `/opt/simba/impalaodbc/lib/64`

folder, depending on the version of the driver that you installed. You must have root privileges when changing the contents of this folder.

Next, configure the environment variables on your machine to make sure that the ODBC driver manager can work with the driver. For more information, see [Configuring the ODBC Driver Manager on Non-Windows Machines](#) on page 41.

Verifying the Driver Version Number on Linux

To verify the driver version number on Linux using the command-line interface:

- Depending on your package manager, at the command prompt, run one of the following commands:

- ```
yum list | grep SimbaImpalaODBC
```

- ```
rpm -qa | grep SimbaImpalaODBC
```

The command returns information about the Simba Impala ODBC Driver that is installed on your machine, including the version number.

To verify the driver version number on Linux using the binary file:

1. Navigate to the `/lib` subfolder in your driver installation directory. By default, the path to this directory is: `/opt/simba/impala/lib`.
2. Open the driver's `.so` binary file in a text editor, and search for the text `$driver_version_sb$:`. The driver's version number is listed after this text.

AIX Driver

AIX System Requirements

The Simba Impala ODBC Driver supports Apache Impala versions 2.8 through 3.3.

Install the driver on client machines where the application is installed. Each machine that you install the driver on must meet the following minimum system requirements:

- IBM AIX 5.3, 6.1, or 7.1
- 150 MB of available disk space
- One of the following ODBC driver managers installed:
 - iODBC 3.52.9 or later
 - unixODBC 2.2.14 or later

To install the driver, you must have root access on the machine.

Installing the Driver on AIX

On 64-bit editions of AIX, you can execute both 32- and 64-bit applications. However, 64-bit applications must use 64-bit drivers, and 32-bit applications must use 32-bit drivers. Make sure that you use the version of the driver that matches the bitness of the client application:

- `SimbaImpalaODBC-32bit-[Version]-[Release].ppc.rpm` for the 32-bit driver
- `SimbaImpalaODBC-[Version]-[Release].ppc.rpm` for the 64-bit driver

[Version] is the version number of the driver, and *[Release]* is the release number for this version of the driver.

You can install both versions of the driver on the same machine.

To install the Simba Impala ODBC Driver on AIX:

1. Log in as the root user, and then navigate to the folder containing the RPM package for the driver.
2. Run the following command from the command line, where *[RPMFileName]* is the file name of the RPM package:

```
rpm --install [RPMFileName]
```

The Simba Impala ODBC Driver files are installed in the `/opt/simba/impala` directory.

3. If you received a license file via email, then copy the license file into the `/opt/simba/impala/lib/32` or `/opt/simba/impala/lib/64` folder, depending on the version of the driver that you installed. You must have root privileges when changing the contents of this folder.

Next, configure the environment variables on your machine to make sure that the ODBC driver manager can work with the driver. For more information, see [Configuring the ODBC Driver Manager on Non-Windows Machines](#) on page 41.

Verifying the Driver Version Number on AIX

If you need to verify the version of the Simba Impala ODBC Driver that is installed on your AIX machine, you can query the version number through the command-line interface.

To verify the driver version number on AIX:

- At the command prompt, run the following command:

```
rpm -qa | grep SimbaImpalaODBC
```

The command returns information about the Simba Impala ODBC Driver that is installed on your machine, including the version number.

Solaris Driver

Solaris System Requirements

The Simba Impala ODBC Driver supports Apache Impala versions 2.8 through 3.3.

Install the driver on client machines where the application is installed. Each machine that you install the driver on must meet the following minimum system requirements:

- Solaris 10 or 11 (SPARC and SPARC64 editions only)
- 50 MB of available disk space
- One of the following ODBC driver managers installed:
 - iODBC 3.52.9 or later
 - unixODBC 2.2.14 or later

To install the driver, you must have root access on the machine.

Installing the Driver on Solaris

The Simba Impala ODBC Driver is available for Solaris as a tarball package named `Simba Impala ODBC Driver_Solaris-gcc_[Version].[Release]_Solaris.tar.gz`, where *[Version]* is the version number of the driver and *[Release]* is the release number for this version of the driver. The package contains both the 32-bit and 64-bit versions of the driver.

On sparc64 editions of Solaris, you can execute both sparc and sparc64 applications. However, sparc64 applications must use 64-bit drivers, and sparc applications must use 32-bit drivers. Make sure that you use the version of the driver that matches the bitness of the client application. You can install both versions of the driver on the same machine.

To install the Simba Impala ODBC Driver on Solaris:

1. Log in as the root user, and then navigate to the folder containing the tarball package.
2. Run the following command to extract the package and install the driver:

```
tar --directory=/opt -zxvf [TarballName]
```

Where *[TarballName]* is the name of the tarball package containing the driver.

The Simba Impala ODBC Driver files are installed in the `/opt/simba/impala/` directory.

3. If you received a license file via email, then copy the license file into the `/opt/simba/impala/lib/32` or `/opt/simba/impala/lib/64` folder, depending on the version of the driver that you installed. You must have root privileges when changing the contents of this folder.

Next, configure the environment variables on your machine to make sure that the ODBC driver manager can work with the driver. For more information, see [Configuring the ODBC Driver Manager on Non-Windows Machines](#) on page 41.

Verifying the Driver Version Number on Solaris

If you need to verify the version of the Simba Impala ODBC Driver that is installed on your Solaris machine, you can query the version number through the command-line interface.

To verify the driver version number on Solaris:

- At the command prompt, run the following command:

```
rpm -qa | grep SimbaImpalaODBC
```

The command returns information about the Simba Impala ODBC Driver that is installed on your machine, including the version number.

Configuring the ODBC Driver Manager on Non-Windows Machines

To make sure that the ODBC driver manager on your machine is configured to work with the Simba Impala ODBC Driver, do the following:

- Set the library path environment variable to make sure that your machine uses the correct ODBC driver manager. For more information, see [Specifying ODBC Driver Managers on Non-Windows Machines](#) on page 41.
- If the driver configuration files are not stored in the default locations expected by the ODBC driver manager, then set environment variables to make sure that the driver manager locates and uses those files. For more information, see [Specifying the Locations of the Driver Configuration Files](#) on page 42.

After configuring the ODBC driver manager, you can configure a connection and access your data store through the driver.

Specifying ODBC Driver Managers on Non-Windows Machines

You need to make sure that your machine uses the correct ODBC driver manager to load the driver. To do this, set the library path environment variable.

macOS

If you are using a macOS machine, then set the `DYLD_LIBRARY_PATH` environment variable to include the paths to the ODBC driver manager libraries. For example, if the libraries are installed in `/usr/local/lib`, then run the following command to set `DYLD_LIBRARY_PATH` for the current user session:

```
export DYLD_LIBRARY_PATH=$DYLD_LIBRARY_PATH:/usr/local/lib
```

For information about setting an environment variable permanently, refer to the macOS shell documentation.

Linux or AIX

If you are using a Linux or AIX machine, then set the `LD_LIBRARY_PATH` environment variable to include the paths to the ODBC driver manager libraries. For example, if the libraries are installed in `/usr/local/lib`, then run the following command to set `LD_LIBRARY_PATH` for the current user session:

```
export LD_LIBRARY_PATH=$LD_LIBRARY_PATH:/usr/local/lib
```

For information about setting an environment variable permanently, refer to the Linux or AIX shell documentation.

Solaris

If you are using a Solaris machine, then set the `LD_LIBRARY_PATH` environment variable to include the paths to the ODBC driver manager libraries and the third-party libraries that are installed with the driver. For example, if the driver manager libraries are installed in `/usr/local/lib` and the 32-bit driver is installed in `/opt/simba/impala`, then run the following command to set `LD_LIBRARY_PATH` for the current user session:

```
export LD_LIBRARY_PATH=$LD_LIBRARY_
PATH:/usr/local/lib:/opt/simba/impala/lib/32
```

For information about setting an environment variable permanently, refer to the Solaris shell documentation.

Specifying the Locations of the Driver Configuration Files

By default, ODBC driver managers are configured to use hidden versions of the `odbc.ini` and `odbcinst.ini` configuration files (named `.odbc.ini` and `.odbcinst.ini`) located in the home directory, as well as the `simba.impalaodbc.ini` file in the `lib` subfolder of the driver installation directory. If you store these configuration files elsewhere, then you must set the environment variables described below so that the driver manager can locate the files.

If you are using iODBC, do the following:

- Set `ODBCINI` to the full path and file name of the `odbc.ini` file.
- Set `ODBCINSTINI` to the full path and file name of the `odbcinst.ini` file.
- Set `SIMBAIMPALAINI` to the full path and file name of the `simba.impalaodbc.ini` file.

If you are using unixODBC, do the following:

- Set `ODBCINI` to the full path and file name of the `odbc.ini` file.
- Set `ODBCSYSINI` to the full path of the directory that contains the `odbcinst.ini` file.

- Set `SIMBAIMPALAINI` to the full path and file name of the `simba.impalaodbc.ini` file.

For example, if your `odbc.ini` and `odbcinst.ini` files are located in `/usr/local/odbc` and your `simba.impalaodbc.ini` file is located in `/etc`, then set the environment variables as follows:

For iODBC:

```
export ODBCINI=/usr/local/odbc/odbc.ini
export ODBCINSTINI=/usr/local/odbc/odbcinst.ini
export SIMBAIMPALAINI=/etc/simba.impalaodbc.ini
```

For unixODBC:

```
export ODBCINI=/usr/local/odbc/odbc.ini
export ODBCDSYSINI=/usr/local/odbc
export SIMBAIMPALAINI=/etc/simba.impalaodbc.ini
```

To locate the `simba.impalaodbc.ini` file, the driver uses the following search order:

1. If the `SIMBAIMPALAINI` environment variable is defined, then the driver searches for the file specified by the environment variable.
2. The driver searches the directory that contains the driver library files for a file named `simba.impalaodbc.ini`.
3. The driver searches the current working directory of the application for a file named `simba.impalaodbc.ini`.
4. The driver searches the home directory for a hidden file named `.simba.impalaodbc.ini` (prefixed with a period).
5. The driver searches the `/etc` directory for a file named `simba.impalaodbc.ini`.

Configuring ODBC Connections on a Non-Windows Machine

The following sections describe how to configure ODBC connections when using the Simba Impala ODBC Driver on non-Windows platforms:

- [Creating a Data Source Name on a Non-Windows Machine](#) on page 44
- [Configuring a DSN-less Connection on a Non-Windows Machine](#) on page 47
- [Configuring Authentication on a Non-Windows Machine](#) on page 49
- [Configuring SSL Verification on a Non-Windows Machine](#) on page 53
- [Configuring Server-Side Properties on a Non-Windows Machine](#) on page 54
- [Configuring Logging Options on a Non-Windows Machine](#) on page 55
- [Setting Driver-Wide Configuration Options on a Non-Windows Machine](#) on page 57
- [Testing the Connection on a Non-Windows Machine](#) on page 58

Creating a Data Source Name on a Non-Windows Machine

Typically, after installing the Simba Impala ODBC Driver, you need to create a Data Source Name (DSN). A DSN is a data structure that stores connection information so that it can be used by the driver to connect to Impala.

You can specify connection settings in a DSN (in the `odbc.ini` file), in a connection string, or as driver-wide settings (in the `simba.impalaodbc.ini` file). Settings in the connection string take precedence over settings in the DSN, and settings in the DSN take precedence over driver-wide settings.

The following instructions describe how to create a DSN by specifying connection settings in the `odbc.ini` file. If your machine is already configured to use an existing `odbc.ini` file, then update that file by adding the settings described below. Otherwise, copy the `odbc.ini` file from the `Setup` subfolder in the driver installation directory to the home directory, and then update the file as described below.

For information about specifying settings in a connection string, see [Configuring a DSN-less Connection on a Non-Windows Machine](#) on page 47 and [Using a Connection String](#) on page 61. For information about driver-wide settings, see [Setting Driver-Wide Configuration Options on a Non-Windows Machine](#) on page 57.

To create a Data Source Name on a non-Windows machine:

1. In a text editor, open the `odbc.ini` configuration file.

Note:

If you are using a hidden copy of the `odbc.ini` file, you can remove the period (.) from the start of the file name to make the file visible while you are editing it.

2. In the `[ODBC Data Sources]` section, add a new entry by typing a name for the DSN, an equal sign (=), and then the name of the driver.

For example, on a macOS machine:

```
[ODBC Data Sources]
Sample DSN=Simba Impala ODBC Driver
```

As another example, for a 32-bit driver on a Linux/AIX/Solaris machine:

```
[ODBC Data Sources]
Sample DSN=Simba Impala ODBC Driver 32-bit
```

3. Create a section that has the same name as your DSN, and then specify configuration options as key-value pairs in the section:
 - a. Set the `Driver` property to the full path of the driver library file that matches the bitness of the application.

For example, on a macOS machine:

```
Driver=/Library/simba/impala/lib/libimpalaodbcodbc_
sbu.dylib
```

As another example, for a 32-bit driver on a Linux/AIX/Solaris machine:

```
Driver=/opt/simba/impala/lib/32/libimpalaodbc_
sb32.so
```

- b. Set the `Host` property to the IP address or host name of the server.

For example:


```
Host=192.168.222.160
```

- c. Set the `Port` property to the number of the TCP port that the server uses to listen for client connections.

For example:

```
Port=21050
```

- d. If authentication is required to access the server, then specify the authentication mechanism and your credentials. For more information, see [Configuring Authentication on a Non-Windows Machine](#) on page 49.
 - e. If you want to connect to the server through SSL, then enable SSL and specify the certificate information. For more information, see [Configuring SSL Verification on a Non-Windows Machine](#) on page 53.
 - f. If you want to configure server-side properties, then set them as key-value pairs using a special syntax. For more information, see [Configuring Server-Side Properties on a Non-Windows Machine](#) on page 54.
 - g. Optionally, set additional key-value pairs as needed to specify other optional connection settings. For detailed information about all the configuration options supported by the Simba Impala ODBC Driver, see [Driver Configuration Options](#) on page 70.
4. Save the `odbc.ini` configuration file.

 **Note:**

If you are storing this file in its default location in the home directory, then prefix the file name with a period (.) so that the file becomes hidden. If you are storing this file in another location, then save it as a non-hidden file (without the prefix), and make sure that the ODBCINI environment variable specifies the location. For more information, see [Specifying the Locations of the Driver Configuration Files](#) on page 42.

For example, the following is an `odbc.ini` configuration file for macOS containing a DSN that connects to an Impala server that does not require authentication:

```
[ODBC Data Sources]
Sample DSN=Simba Impala ODBC Driver
[Sample DSN]
Driver=/Library/simba/impala/lib/libimpalaodbcodbc_sbu.dylib
Host=192.168.222.160
Port=21050
```

As another example, the following is an `odbc.ini` configuration file for a 32-bit driver on a Linux/AIX/Solaris machine, containing a DSN that connects to an Impala server that does not require authentication:

```
[ODBC Data Sources]
Sample DSN=Simba Impala ODBC Driver 32-bit
[Sample DSN]
Driver=/opt/simba/impala/lib/32/libimpalaodbc_sb32.so
```

```
Host=192.168.222.160  
Port=21050
```

You can now use the DSN in an application to connect to the data store.


Configuring a DSN-less Connection on a Non-Windows Machine

To connect to your data store through a DSN-less connection, you need to define the driver in the `odbcinst.ini` file and then provide a DSN-less connection string in your application.

If your machine is already configured to use an existing `odbcinst.ini` file, then update that file by adding the settings described below. Otherwise, copy the `odbcinst.ini` file from the `Setup` subfolder in the driver installation directory to the home directory, and then update the file as described below.

To define a driver on a non-Windows machine:

1. In a text editor, open the `odbcinst.ini` configuration file.

 **Note:**

If you are using a hidden copy of the `odbcinst.ini` file, you can remove the period (.) from the start of the file name to make the file visible while you are editing it.

2. In the `[ODBC Drivers]` section, add a new entry by typing a name for the driver, an equal sign (=), and then `Installed`.

For example:

```
[ODBC Drivers]  
Simba Impala ODBC Driver=Installed
```

3. Create a section that has the same name as the driver (as specified in the previous step), and then specify the following configuration options as key-value pairs in the section:
 - a. Set the `Driver` property to the full path of the driver library file that matches the bitness of the application.

For example, on a macOS machine:

```
Driver=/Library/simba/impala/lib/libimpalaodbc_  
sbu.dylib
```

As another example, for a 32-bit driver on a Linux/AIX/Solaris machine:


```
Driver=/opt/simba/impala/lib/32/libimpalaodbc_
sb32.so
```

- b. Optionally, set the `Description` property to a description of the driver.

For example:

```
Description=Simba Impala ODBC Driver
```

4. Save the `odbcinst.ini` configuration file.

 **Note:**

If you are storing this file in its default location in the home directory, then prefix the file name with a period (.) so that the file becomes hidden. If you are storing this file in another location, then save it as a non-hidden file (without the prefix), and make sure that the `ODBCINSTINI` or `ODBCSYSINI` environment variable specifies the location. For more information, see [Specifying the Locations of the Driver Configuration Files](#) on page 42.

For example, the following is an `odbcinst.ini` configuration file for macOS:

```
[ODBC Drivers]
Simba Impala ODBC Driver=Installed
[Simba Impala ODBC Driver]
Description=Simba Impala ODBC Driver
Driver=/Library/simba/impala/lib/libimpalaodbc_sbu.dylib
```

As another example, the following is an `odbcinst.ini` configuration file for both the 32- and 64-bit drivers on Linux/AIX/Solaris:

```
[ODBC Drivers]
Simba Impala ODBC Driver 32-bit=Installed
Simba Impala ODBC Driver 64-bit=Installed
[Simba Impala ODBC Driver 32-bit]
Description=Simba Impala ODBC Driver (32-bit)
Driver=/opt/simba/impala/lib/32/libimpalaodbc_sb32.so
[Simba Impala ODBC Driver 64-bit]
Description=Simba Impala ODBC Driver (64-bit)
Driver=/opt/simba/impala/lib/64/libimpalaodbc_sb64.so
```

You can now connect to your data store by providing your application with a connection string where the `Driver` property is set to the driver name specified in the `odbcinst.ini` file, and all the other necessary connection properties are also set.

For more information, see "DSN-less Connection String Examples" in [Using a Connection String](#) on page 61.

For instructions about configuring specific connection features, see the following:

- [Configuring Authentication on a Non-Windows Machine](#) on page 49
- [Configuring SSL Verification on a Non-Windows Machine](#) on page 53
- [Configuring Server-Side Properties on a Non-Windows Machine](#) on page 54

For detailed information about all the connection properties that the driver supports, see [Driver Configuration Options](#) on page 70.

Configuring Authentication on a Non-Windows Machine

Some Impala servers are configured to require authentication for access. To connect to an Impala server, you must configure the Simba Impala ODBC Driver to use the authentication mechanism that matches the access requirements of the server and provides the necessary credentials.

For information about how to determine the type of authentication your Impala server requires, see [Authentication Options](#) on page 60.

You can set the connection properties for authentication in a connection string, in a DSN (in the `odbc.ini` file), or as a driver-wide setting (in the `simba.impalaodbc.ini` file). Settings in the connection string take precedence over settings in the DSN, and settings in the DSN take precedence over driver-wide settings.

The following authentication methods are available:

- [Using No Authentication](#) on page 50
- [Using Kerberos](#) on page 50
- [Using Advanced Kerberos](#) on page 51
- [Using SASL User Name](#) on page 52
- [Using User Name And Password](#) on page 53

If cookie-based authentication is enabled in your Impala database, you can specify a list of authentication cookies in the `HTTPAuthCookies` connection property. In this case, the driver authenticates the connection once based on the provided authentication credentials. It then uses the cookie generated by the server for each subsequent request in the same connection. For more information, see [HTTPAuthCookies](#) on page 98.

Using No Authentication

For this authentication mechanism, you do not need to configure any additional settings.

Note:

The default configuration of Impala requires the Simba Impala ODBC Driver to be configured to use the No Authentication mechanism.

To configure a connection without authentication:

- Set the `AuthMech` connection attribute to 0.

Using Kerberos

Kerberos must be installed and configured before you can use this authentication mechanism. For more information, refer to the MIT Kerberos Documentation: <http://web.mit.edu/kerberos/krb5-latest/doc/>.

To configure Kerberos authentication:

1. Set the `AuthMech` connection attribute to 1.
2. Choose one:
 - To use the default realm defined in your Kerberos setup, do not set the `KrbRealm` attribute.
 - Or, if your Kerberos setup does not define a default realm or if the realm of your Impala server is not the default, then set the appropriate realm using the `KrbRealm` attribute.
3. Optionally, if you are using MIT Kerberos and a Kerberos realm is specified using the `KrbRealm` connection attribute, then choose one:
 - To have the Kerberos layer canonicalize the server's service principal name, leave the `ServicePrincipalCanonicalization` attribute set to 1.
 - Or, to prevent the Kerberos layer from canonicalizing the server's service principal name, set the `ServicePrincipalCanonicalization` attribute to 0.
4. Set the `KrbFQDN` attribute to the fully qualified domain name of the Impala server host.

Note:

To use the Impala server host name as the fully qualified domain name for Kerberos authentication, set `KrbFQDN` to `_HOST`.

5. Set the `KrbServiceName` attribute to the service name of the Impala server.
6. Optionally, set the `TSaslTransportBufSize` attribute to the number of bytes to reserve in memory for buffering unencrypted data from the network.

 **Note:**

In most circumstances, the default value of 1000 bytes is optimal.

Using Advanced Kerberos

This authentication mechanism allows concurrent connections within the same process to use different Kerberos user principals.

When you use Advanced Kerberos authentication, you do not need to run the `kinit` command to obtain a Kerberos ticket. Instead, you use a JSON file to map your Impala user name to a Kerberos user principal name and a keytab that contains the corresponding keys. The driver obtains Kerberos tickets based on the specified mapping. As a fallback, you can specify a keytab that the driver uses by default if the mapping file is not available or if no matching keytab can be found in the mapping file.

 **Note:**

- For information about the schema of the mapping file and how the driver handles invalid mappings, see [UPN Keytab Mapping File](#) on page 89.
- For information about how the driver searches for a keytab file if the keytab mapping and default keytab file are invalid, see [Default Keytab File](#) on page 75.

To configure Advanced Kerberos authentication:


1. Set the `AuthMech` connection attribute to 1.
2. Choose one:
 - To use the default realm defined in your Kerberos setup, do not set the `KrbRealm` attribute.
 - Or, if your Kerberos setup does not define a default realm or if the realm of your Impala server is not the default, then set the appropriate realm using the `KrbRealm` attribute.
3. Optionally, if you are using MIT Kerberos and a Kerberos realm is specified using the `KrbRealm` connection attribute, then choose one:
 - To have the Kerberos layer canonicalize the server's service principal name, leave the `ServicePrincipalCanonicalization` attribute set to 1.

- Or, to prevent the Kerberos layer from canonicalizing the server's service principal name, set the `ServicePrincipalCanonicalization` attribute to 0.
4. Set the `KrbFQDN` attribute to the fully qualified domain name of the Impala server host.

 **Note:**

To use the Impala server host name as the fully qualified domain name for Kerberos authentication, set `KrbFQDN` to `_HOST`.

5. Set the `KrbServiceName` attribute to the service name of the Impala server.
6. Set the `UseKeytab` attribute to 1.
7. Set the `UID` attribute to an appropriate user name for accessing the Impala server.
8. Set the `UPNKeytabMappingFile` attribute to the full path to a JSON file that maps your Impala user name to a Kerberos user principal name and a keytab file.
9. Set the `DefaultKeytabFile` attribute to the full path to a keytab file that the driver can use if the mapping file is not available or if no matching keytab can be found in the mapping file.
10. If the Impala server is configured to use SSL, then configure SSL for the connection. For more information, see [Configuring SSL Verification on a Non-Windows Machine](#) on page 53.
11. Optionally, set the `TSaslTransportBufSize` attribute to the number of bytes to reserve in memory for buffering unencrypted data from the network.

 **Note:**

In most circumstances, the default value of 1000 bytes is optimal.

Using SASL User Name

This authentication mechanism requires a user name but does not require a password. The user name labels the session, facilitating database tracking.

To configure SASL User Name authentication:

1. Set the `AuthMech` connection attribute to 2.
2. Set the `UID` attribute to an appropriate user name for accessing the Impala server.
3. Optionally, set the `TSaslTransportBufSize` attribute to the number of bytes to reserve in memory for buffering unencrypted data from the network.

 **Note:**

In most circumstances, the default value of 1000 bytes is optimal.

Using User Name And Password


This authentication mechanism requires a user name and a password.

 **Note:**

This authentication mechanism should not be used with an Impala configuration that does not have LDAP enabled.

To configure User Name And Password authentication:

1. Set the `AuthMech` connection attribute to 3.
2. Set the `UID` attribute to an appropriate user name for accessing the Impala server.
3. Set the `PWD` attribute to the password corresponding to the user name you provided above.
4. Optionally, set the `TSaslTransportBufSize` attribute to the number of bytes to reserve in memory for buffering unencrypted data from the network.

 **Note:**

In most circumstances, the default value of 1000 bytes is optimal.

5. Optionally, to use SASL to handle authentication, set the `UseSASL` attribute to 1.

 **Note:**

If the Transport Mode property is specified, it takes precedence over this property.

Configuring SSL Verification on a Non-Windows Machine

If you are connecting to an Impala server that has Secure Sockets Layer (SSL) enabled, you can configure the driver to connect to an SSL-enabled socket. When using SSL to connect to a server, the driver can be configured to verify the identity of the server.

You can set the connection properties described below in a connection string, in a DSN (in the `odbc.ini` file), or as a driver-wide setting (in the `simba.impalaodbc.ini` file). Settings in the connection string take precedence

over settings in the DSN, and settings in the DSN take precedence over driver-wide settings.

To configure SSL verification on a non-Windows machine:

1. To enable SSL connections, set the `SSL` attribute to 1.
2. To allow authentication using self-signed certificates that have not been added to the list of trusted certificates, set the `AllowSelfSignedServerCert` attribute to 1.
3. To allow the common name of a CA-issued SSL certificate to not match the host name of the Impala server, set the `AllowHostNameCNMismatch` attribute to 1.
4. Choose one:
 - To configure the driver to load SSL certificates from a specific `.pem` file when verifying the server, set the `TrustedCerts` attribute to the full path of the `.pem` file.
 - Or, to use the trusted CA certificates `.pem` file that is installed with the driver, do not specify a value for the `TrustedCerts` attribute.
5. To specify the minimum version of TLS to use, set the `Min_TLS` property to the minimum version of TLS. Supported options include `1.0` for TLS 1.0, `1.1` for TLS 1.1, and `1.2` for TLS 1.2.

Configuring Server-Side Properties on a Non-Windows Machine

When connecting to a server that is running Impala 2.0 or later, you can use the driver to apply configuration properties to the Impala server.

You can set the connection properties described below in a connection string, in a DSN (in the `odbc.ini` file), or as a driver-wide setting (in the `simba.impalaodbc.ini` file). Settings in the connection string take precedence over settings in the DSN, and settings in the DSN take precedence over driver-wide settings.

! Important:

This feature is not supported for earlier versions of Impala, where the `SET` statement can only be executed from within the Impala shell.

To configure server-side properties on a non-Windows machine:

1. To set a server-side property, use the syntax `SSP_[SSPKey]=[SSPValue]`, where `[SSPKey]` is the name of the server-side property and `[SSPValue]` is the value to specify for that property. For example, to set the `MEM_LIMIT` query

option to 1 GB and the `REQUEST_POOL` query option to `myPool`, type the following in the `odbc.ini` file:

```
SSP_MEM_LIMIT=1000000000
SSP_REQUEST_POOL=myPool
```

Or, to set those properties in a connection string, type the following:

```
SSP_MEM_LIMIT={1000000000};SSP_REQUEST_POOL={myPool}
```

 **Note:**

When setting a server-side property in a connection string, it is recommended that you enclose the value in braces (`{ }`) to make sure that special characters can be properly escaped.

2. To disable the driver's default behavior of converting server-side property key names to all lower-case characters, set the `LCaseSspKeyName` property to 0.

Configuring Logging Options on a Non-Windows Machine

To help troubleshoot issues, you can enable logging in the driver.

! Important:

- Only enable logging long enough to capture an issue. Logging decreases performance and can consume a large quantity of disk space.
- The settings for logging apply to every connection that uses the Simba Impala ODBC Driver, so make sure to disable the feature after you are done using it.

Logging is configured through driver-wide settings in the `simba.impalaodbc.ini` file, which apply to all connections that use the driver.

To enable logging on a non-Windows machine:

1. Open the `simba.impalaodbc.ini` configuration file in a text editor.
2. To specify the level of information to include in log files, set the `LogLevel` property to one of the following numbers:

LogLevel Value	Description
0	Disables all logging.
1	Logs severe error events that lead the driver to abort.
2	Logs error events that might allow the driver to continue running.
3	Logs events that might result in an error if action is not taken.
4	Logs general information that describes the progress of the driver.
5	Logs detailed information that is useful for debugging the driver.
6	Logs all driver activity.

3. Set the `LogPath` key to the full path to the folder where you want to save log files.
4. Set the `LogFileCount` key to the maximum number of log files to keep.

 **Note:**

After the maximum number of log files is reached, each time an additional file is created, the driver deletes the oldest log file.

5. Set the `LogFileSize` key to the maximum size of each log file in bytes.

 **Note:**

After the maximum file size is reached, the driver creates a new file and continues logging.

6. Optionally, to prefix the log file name with the user name and process ID associated with the connection, set the `UseLogPrefix` property to 1.
7. Save the `simba.impalaodbc.ini` configuration file.
8. Restart your ODBC application to make sure that the new settings take effect.

The Simba Impala ODBC Driver produces the following log files at the location you specify using the `LogPath` key:

- A `simbaimpalaodbcdriver.log` file that logs driver activity that is not specific to a connection.
- A `simbaimpalaodbcdriver_connection_[Number].log` file for each connection made to the database, where `[Number]` is a number that identifies each log file. This file logs driver activity that is specific to the connection.

If you set the `UseLogPrefix` property to 1, then each file name is prefixed with `[UserName]_[ProcessID]_`, where `[UserName]` is the user name associated with the connection and `[ProcessID]` is the process ID of the application through which the connection is made. For more information, see [UseLogPrefix](#) on page 101.

To disable logging on a non-Windows machine:

1. Open the `simba.impalaodbc.ini` configuration file in a text editor.
2. Set the `LogLevel` key to 0.
3. Save the `simba.impalaodbc.ini` configuration file.
4. Restart your ODBC application to make sure that the new settings take effect.

Setting Driver-Wide Configuration Options on a Non-Windows Machine

When you specify connection settings in a DSN or connection string, those settings apply only when you connect to Impala using that particular DSN or string. As an alternative, you can specify settings that apply to every connection that uses the Simba Impala ODBC Driver by configuring them in the `simba.impalaodbc.ini` file.

Note:

Settings in the connection string take precedence over settings in the DSN, and settings in the DSN take precedence over driver-wide settings.

To set driver-wide configuration options on a non-Windows machine:

1. In a text editor, open the `simba.impalaodbc.ini` configuration file.
2. In the `[Driver]` section, specify configuration options as key-value pairs. Start a new line for each key-value pair.

For example, to enable SASL User Name authentication using "simba" as the user name, type the following:

```
AuthMech=2
UID=simba
```

For detailed information about all the configuration options supported by the driver, see [Driver Configuration Options](#) on page 70.

3. Save the `simba.impalaodbc.ini` configuration file.

Testing the Connection on a Non-Windows Machine

To test the connection, you can use an ODBC-enabled client application. For a basic connection test, you can also use the test utilities that are packaged with your driver manager installation. For example, the iODBC driver manager includes simple utilities called `iodbctest` and `iodbctestw`. Similarly, the unixODBC driver manager includes simple utilities called `isql` and `iusql`.

Using the iODBC Driver Manager

You can use the `iodbctest` and `iodbctestw` utilities to establish a test connection with your driver. Use `iodbctest` to test how your driver works with an ANSI application, or use `iodbctestw` to test how your driver works with a Unicode application.

Note:

There are 32-bit and 64-bit installations of the iODBC driver manager available. If you have only one or the other installed, then the appropriate version of `iodbctest` (or `iodbctestw`) is available. However, if you have both 32- and 64-bit versions installed, then you need to make sure that you are running the version from the correct installation directory.

For more information about using the iODBC driver manager, see <http://www.iodbc.org>.

To test your connection using the iODBC driver manager:

1. Run **`iodbctest`** or **`iodbctestw`**.
2. Optionally, if you do not remember the DSN, then type a question mark (?) to see a list of available DSNs.
3. Type the connection string for connecting to your data store, and then press ENTER. For more information, see [Using a Connection String](#) on page 61.

If the connection is successful, then the `SQL>` prompt appears.

Using the unixODBC Driver Manager

You can use the `isql` and `iusql` utilities to establish a test connection with your driver and your DSN. `isql` and `iusql` can only be used to test connections that use a DSN.

Use `isql` to test how your driver works with an ANSI application, or use `iusql` to test how your driver works with a Unicode application.

 **Note:**

There are 32-bit and 64-bit installations of the unixODBC driver manager available. If you have only one or the other installed, then the appropriate version of `isql` (or `iusql`) is available. However, if you have both 32- and 64-bit versions installed, then you need to make sure that you are running the version from the correct installation directory.

For more information about using the unixODBC driver manager, see <http://www.unixodbc.org>.

To test your connection using the unixODBC driver manager:

➤ Run `isql` or `iusql` by using the corresponding syntax:

- `isql [DataSourceName]`
- `iusql [DataSourceName]`

`[DataSourceName]` is the DSN that you are using for the connection.

If the connection is successful, then the `SQL>` prompt appears.

 **Note:**

For information about the available options, run `isql` or `iusql` without providing a DSN.

Authentication Options

Impala supports multiple authentication mechanisms. You must determine the authentication type that your server is using. The authentication methods available in the Simba Impala ODBC Driver are as follows:

- No Authentication
- Kerberos
- SASL User Name
- User Name And Password

 **Note:**

- The default configuration of Impala requires the Simba Impala ODBC Driver to be configured to use the No Authentication mechanism.
- In addition to regular Kerberos authentication, the driver also supports an advanced configuration of Kerberos authentication that allows concurrent connections within the same process to use different Kerberos user principals.

In addition to authentication, you can configure the driver to connect over SSL or use SASL to handle authentication.

The Impala server uses SASL (Simple Authentication and Security Layer) to support some of the authentication methods. Kerberos is supported with the SASL GSSAPI mechanism. SASL User Name and User Name And Password (with SASL enabled) are supported with the SASL PLAIN mechanism.

SASL mechanisms	Non-SASL mechanisms
<ul style="list-style-type: none"> • Kerberos • SASL User Name • User Name And Password (with SASL enabled) 	<ul style="list-style-type: none"> • No Authentication • User Name And Password (without SASL enabled)

 **Note:**

Thrift (the layer for handling remote process communication between the Simba Impala ODBC Driver and the Impala server) has a limitation where it cannot detect a mix of non-SASL and SASL mechanisms being used between the driver and the server. If this happens, the driver will appear to hang during connection establishment.

Using a Connection String

For some applications, you might need to use a connection string to connect to your data source. For detailed information about how to use a connection string in an ODBC application, refer to the documentation for the application that you are using.

The connection strings in the following sections are examples showing the minimum set of connection attributes that you must specify to successfully connect to the data source. Depending on the configuration of the data source and the type of connection you are working with, you might need to specify additional connection attributes. For detailed information about all the attributes that you can use in the connection string, see [Driver Configuration Options](#) on page 70.

DSN Connection String Example

The following is an example of a connection string for a connection that uses a DSN:

```
DSN= [DataSourceName]
```

[DataSourceName] is the DSN that you are using for the connection.

You can set additional configuration options by appending key-value pairs to the connection string. Configuration options that are passed in using a connection string take precedence over configuration options that are set in the DSN.

DSN-less Connection String Examples

Some applications provide support for connecting to a data source using a driver without a DSN. To connect to a data source without using a DSN, use a connection string instead.

The placeholders in the examples are defined as follows, in alphabetical order:

- *[DomainName]* is the fully qualified domain name of the Impala server host.
- *[MappingFile]* is the full path to a JSON file that maps your Impala user name to a Kerberos user principal name and a keytab file.
- *[PortNumber]* is the number of the TCP port that the Impala server uses to listen for client connections.
- *[Realm]* is the Kerberos realm of the Impala server host.
- *[Server]* is the IP address or host name of the Impala server to which you are connecting.
- *[ServiceName]* is the Kerberos service principal name of the Impala server.

- *[YourPassword]* is the password corresponding to your user name.
- *[YourUserName]* is the user name that you use to access the Impala server.

Connecting to an Impala Server Without Authentication

The following is the format of a DSN-less connection string that connects to an Impala server that does not require authentication:

```
Driver=Simba Impala ODBC Driver;Host=[Server];  
Port=[PortNumber];
```

For example:

```
Driver=Simba Impala ODBC Driver;Host=192.168.222.160;  
Port=21050;
```

If you are connecting to the server through SSL, then set the `SSL` property to 1. For example:

```
Driver=Simba Impala ODBC Driver;Host=192.168.222.160;  
Port=21050;SSL=1;
```

Connecting to an Impala Server that Requires Kerberos Authentication

The following is the format of a DSN-less connection string that connects to an Impala server requiring Kerberos authentication:

```
Driver=Simba Impala ODBC Driver;Host=[Server];  
Port=[PortNumber];AuthMech=1;KrbRealm=[Realm];  
KrbFQDN=[DomainName];KrbServiceName=[ServiceName];
```

For example:

```
Driver=Simba Impala ODBC Driver;Host=192.168.222.160;  
Port=21050;AuthMech=1;KrbRealm=SIMBA;  
KrbFQDN=localhost.localdomain;KrbServiceName=impala;
```

If you are connecting to the server through SSL, then set the `SSL` property to 1. For example:

```
Driver=Simba Impala ODBC Driver;Host=192.168.222.160;  
Port=21050;AuthMech=1;KrbRealm=SIMBA;  
KrbFQDN=localhost.localdomain;KrbServiceName=impala;SSL=1;
```

Connecting to an Impala Server using Advanced Kerberos Authentication

The following is the format of a DSN-less connection string that connects to an Impala server using Advanced Kerberos authentication:

```
Driver=Simba Impala ODBC Driver;Host=[Server];
Port=[PortNumber];AuthMech=1;KrbRealm=[Realm];
KrbFQDN=[DomainName];KrbServiceName=[ServiceName];
UseKeytab=1;UID=[YourUserName];
UPNKeytabMappingFile=[MappingFile];
```

For example:

```
Driver=Simba Impala ODBC Driver;Host=192.168.222.160;
Port=21050;AuthMech=1;KrbRealm=SIMBA;
KrbFQDN=localhost.localdomain;KrbServiceName=impala;
UseKeytab=1;UID=simba;
UPNKeytabMappingFile=C:\Temp\simba.keytab;
```

If you are connecting to the server through SSL, then set the SSL property to 1. For example:

```
Driver=Simba Impala ODBC Driver;Host=192.168.222.160;
Port=21050;AuthMech=1;KrbRealm=SIMBA;
KrbFQDN=localhost.localdomain;KrbServiceName=impala;
UseKeytab=1;UID=simba;
UPNKeytabMappingFile=C:\Temp\simba.keytab;SSL=1;
```

Connecting to an Impala Server that Requires User Name Authentication

The following is the format of a DSN-less connection string that connects to an Impala server requiring User Name authentication. By default, the driver uses **anonymous** as the user name.

```
Driver=Simba Impala ODBC Driver;Host=[Server];
Port=[PortNumber];AuthMech=2;
```

For example:

```
Driver=Simba Impala ODBC Driver;Host=192.168.222.160;
Port=21050;AuthMech=2;
```

If you are connecting to the server through SSL, then set the `SSL` property to 1. For example:

```
Driver=Simba Impala ODBC Driver;Host=192.168.222.160;  
Port=21050;AuthMech=2;SSL=1;
```

Connecting to an Impala Server with LDAP Authentication or other User Name and Password Authentication Enabled

The following is the format of a DSN-less connection string that connects to an Impala server with LDAP authentication, or another form of username/password authentication, enabled:

```
Driver=Simba Impala ODBC Driver;Host=[Server];  
Port=[PortNumber];AuthMech=3;UID=[UserName];  
PWD=[Password];
```

For example:

```
Driver=Simba Impala ODBC Driver;Host=192.168.222.160;  
Port=21050;AuthMech=3;UID=simba;PWD=simba;
```

If you are connecting to the LDAP-enabled server through SSL, then set the `SSL` property to 1. For example:

```
Driver=Simba Impala ODBC Driver;Host=192.168.222.160;  
Port=21050;AuthMech=3;UID=simba;PWD=simba;SSL=1;
```


Features



For more information on the features of the Simba Impala ODBC Driver, see the following:




- [Data Types](#) on page 65
- [Catalog and Schema Support](#) on page 67
- [SQL Translation](#) on page 67
- [Server-Side Properties](#) on page 67
- [Active Directory](#) on page 68
- [Write-back](#) on page 68
- [Security and Authentication](#) on page 68



Data Types

The Simba Impala ODBC Driver supports many common data formats, converting between Impala data types and SQL data types.

The table below lists the supported data type mappings.

Impala Type	SQL Type
ARRAY	SQL_VARCHAR
BIGINT	SQL_BIGINT
BOOLEAN	SQL_BOOLEAN
CHAR	SQL_CHAR
<p> Note: Only available in CDH 5.2 or later.</p>	<p> Note: SQL_WCHAR is returned instead if the Use SQL Unicode Types configuration option (the UseUnicodeSqlCharacterTypes key) is enabled.</p>

Impala Type	SQL Type
DATE <div data-bbox="228 338 789 499" style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> Note: DATE data types are only supported in Impala 3.3 or later.</p> </div>	SQL_DATE
DECIMAL <div data-bbox="228 600 789 720" style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> Note: Only available in CDH 5.2 or later.</p> </div>	SQL_DECIMAL
DOUBLE <div data-bbox="228 825 789 945" style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> Note: REAL is an alias for DOUBLE.</p> </div>	SQL_DOUBLE
FLOAT	SQL_REAL
INT	SQL_INTEGER
MAP	SQL_VARCHAR
SMALLINT	SQL_SMALLINT
STRUCT	SQL_VARCHAR
TIMESTAMP	SQL_TIMESTAMP
TINYINT	SQL_TINYINT


Impala Type	SQL Type
VARCHAR <div data-bbox="228 338 787 457" style="border: 1px solid gray; padding: 5px; margin-top: 10px;"> <p> Note: Only available in CDH 5.2 or later.</p> </div>	SQL_VARCHAR <div data-bbox="841 338 1399 619" style="border: 1px solid gray; padding: 5px; margin-top: 10px;"> <p> Note: SQL_WVARCHAR is returned instead if the Use SQL Unicode Types configuration option (the UseUnicodeSqlCharacterTypes key) is enabled.</p> </div>

Catalog and Schema Support

The Simba Impala ODBC Driver supports both catalogs and schemas to make it easy for the driver to work with various ODBC applications. Since Impala only organizes tables into schemas/databases, the driver provides a synthetic catalog named IMPALA under which all of the schemas/databases are organized. The driver also maps the ODBC schema to the Impala schema/database.

SQL Translation

The Simba Impala ODBC Driver can parse queries locally before sending them to the Impala server. This feature allows the driver to calculate query metadata without executing the query, support query parameters, and support extra SQL features such as ODBC escape sequences and additional scalar functions that are not available in the Impala-shell tool.

 **Note:**
The driver does not support translation for queries that reference a field contained in a nested column (an ARRAY, MAP, or STRUCT column). To retrieve data from a nested column, make sure that the query is written in valid Impala SQL syntax.

Server-Side Properties

The Simba Impala ODBC Driver allows you to set server-side properties via a DSN. Server-side properties specified in a DSN affect only the connection that is established using the DSN.

For more information about setting server-side properties when using the Windows driver, see [Configuring Server-Side Properties on Windows](#) on page 21. For

information about setting server-side properties when using the driver on a non-Windows platform, see [Configuring Server-Side Properties on a Non-Windows Machine](#) on page 54.

Active Directory

The Simba Impala ODBC Driver supports Active Directory Kerberos on Windows. There are two prerequisites for using Active Directory Kerberos on Windows:

- MIT Kerberos is not installed on the client Windows machine.
- The MIT Kerberos Hadoop realm has been configured to trust the Active Directory realm, according to Apache's documentation, so that users in the Active Directory realm can access services in the MIT Kerberos Hadoop realm.

Write-back

The Simba Impala ODBC Driver supports translation for the following syntax:

- INSERT
- CREATE
- DROP

The driver also supports translation for UPDATE and DELETE syntax, but only when querying Kudu tables while connected to an Impala server that is running Impala 2.7 or later.

If the statement contains non-standard SQL-92 syntax, then the driver is unable to translate the statement to SQL and instead falls back to using Impala SQL.

Security and Authentication

To protect data from unauthorized access, some Impala data stores require connections to be authenticated with user credentials or encrypted using the SSL protocol. The Simba Impala ODBC Driver provides full support for these authentication protocols.

Note:

In this documentation, "SSL" refers to both TLS (Transport Layer Security) and SSL (Secure Sockets Layer). The driver supports TLS 1.0, 1.1, and 1.2. The SSL version used for the connection is the highest version that is supported by both the driver and the server.

The driver provides mechanisms that enable you to authenticate your connection using the Kerberos protocol, your Impala user name only, or your Impala user name and password. You must use the authentication mechanism that matches the security requirements of the Impala server. For information about determining the appropriate authentication mechanism to use based on the Impala server configuration, see [Authentication Options](#) on page 60. For detailed driver configuration instructions, see [Configuring Authentication on Windows](#) on page 12 or [Configuring Authentication on a Non-Windows Machine](#) on page 49.

Additionally, the driver supports SSL connections with or without one-way authentication. If the server has an SSL-enabled socket, then you can configure the driver to connect to it.

It is recommended that you enable SSL whenever you connect to a server that is configured to support it. SSL encryption protects data and credentials when they are transferred over the network, and provides stronger security than authentication alone. For detailed configuration instructions, see [Configuring SSL Verification on Windows](#) on page 18 or [Configuring SSL Verification on a Non-Windows Machine](#) on page 53.


Driver Configuration Options

Driver Configuration Options lists the configuration options available in the Simba Impala ODBC Driver alphabetically by field or button label. Options having only key names, that is, not appearing in the user interface of the driver, are listed alphabetically by key name.

When creating or configuring a connection from a Windows machine, the fields and buttons are available in the following dialog boxes:

- Simba Impala ODBC Driver DSN Setup
- Advanced Options
- Keytab Options
- Server Side Properties
- SSL Options

When using a connection string, configuring driver-wide settings, or configuring a connection from a non-Windows machine, use the key names provided.

 **Note:**

Settings in the connection string take precedence over settings in the DSN, and settings in the DSN take precedence over driver-wide settings.

Configuration Options Appearing in the User Interface

The following configuration options are accessible via the Windows user interface for the Simba Impala ODBC Driver, or via the key name when using a connection string, configuring driver-wide settings, or configuring a connection from a Linux/macOS/AIX/Solaris machine:

- [Allow Common Name Host Name Mismatch](#) on page 71
- [Allow Self-Signed Server Certificate](#) on page 72
- [Async Exec Poll Interval](#) on page 72
- [Canonicalize Principal FQDN](#) on page 73
- [Proxy Host](#) on page 83
- [Proxy Password](#) on page 83
- [Proxy Port](#) on page 83
- [Proxy Username](#) on page 84
- [Realm](#) on page 84
- [Restrict Metadata with Current Schema](#) on page 84
- [Result Set Cache Size](#) on page 85


- [Check Certificate Revocation](#) on page 73
- [Convert Key Name to Lower Case](#) on page 74
- [Database](#) on page 74
- [Default Keytab File](#) on page 75
- [Delegation UID](#) on page 75
- [Enable Auto Reconnect](#) on page 76
- [Enable Query Retry](#) on page 76
- [Enable SSL](#) on page 76
- [Host](#) on page 77
- [Host FQDN](#) on page 78
- [HTTP Path](#) on page 77
- [Ignore Transactions](#) on page 78
- [Log Level](#) on page 78
- [Log Path](#) on page 80
- [Max File Size](#) on page 80
- [Max Number Files](#) on page 81
- [Maximum Retries](#) on page 81
- [Mechanism](#) on page 81
- [Minimum TLS](#) on page 82
- [Password](#) on page 82
- [Port](#) on page 82
- [Retry Interval](#) on page 85
- [Rows Fetched Per Block](#) on page 86
- [Save Password \(Encrypted\)](#) on page 86
- [Service Name](#) on page 86
- [Socket Timeout](#) on page 87
- [String Column Length](#) on page 87
- [Transport Buffer Size](#) on page 87
- [Transport Mode](#) on page 88
- [Trusted Certificates](#) on page 89
- [UPN Keytab Mapping File](#) on page 89
- [Use Keytab](#) on page 90
- [Use Native Query](#) on page 91
- [Use Only SSPI](#) on page 92
- [Use Proxy](#) on page 92
- [Use Simple Authentication and Security Layer \(SASL\)](#) on page 93
- [Use SQL Unicode Types](#) on page 93
- [Use System Trust Store](#) on page 94
- [User Name](#) on page 95

Allow Common Name Host Name Mismatch

Key Name	Default Value	Required
AllowHostNameCNMismatch	Clear (0)	No

Description

This option specifies whether a CA-issued SSL certificate name must match the host name of the Impala server.

 **Note:**

The key for this option used to be `CAIssuedCertNamesMismatch`, and is still recognized by the driver under that key. If both keys are defined, `AllowHostNameCNMismatch` will take precedence.

- Enabled (1): The driver allows a CA-issued SSL certificate name to not match the host name of the Impala server.
- Disabled (0): The CA-issued SSL certificate name must match the host name of the Impala server.

 **Note:**

This setting is applicable only when SSL is enabled.

Allow Self-Signed Server Certificate

Key Name	Default Value	Required
<code>AllowSelfSignedServerCert</code>	Clear (0)	No

Description

This option specifies whether the driver allows a connection to an Impala server that uses a self-signed certificate.

- Enabled (1): The driver authenticates the Impala server even if the server is using a self-signed certificate.
- Disabled (0): The driver does not allow self-signed certificates from the server.

 **Note:**

This setting is applicable only when SSL is enabled.

Async Exec Poll Interval

Key Name	Default Value	Required
<code>AsyncExecPollInterval</code>	10	No

Description

The time in milliseconds between each poll for the query execution status.

"Asynchronous execution" refers to the fact that the RPC call used to execute a query against Impala is asynchronous. It does not mean that ODBC asynchronous operations are supported.

Canonicalize Principal FQDN

Key Name	Default Value	Required
ServicePrincipal Canonicalization	Selected (1)	No

Description

This option specifies whether the Kerberos layer canonicalizes the host FQDN in the server's service principal name.

- Enabled (1): The Kerberos layer canonicalizes the host FQDN in the server's service principal name.
- Disabled (0): The Kerberos layer does not canonicalize the host FQDN in the server's service principal name.

Note:

- This option only affects MIT Kerberos, and is ignored when using Active Directory Kerberos.
- This option can only be disabled if the Kerberos Realm or `KrbRealm` key is specified.

Check Certificate Revocation


Key Name	Default Value	Required
CheckCertRevocation	Selected (1)	No

Description

This option specifies whether the driver checks to see if a certificate has been revoked while retrieving a certificate chain from the Windows Trust Store.

This option is only applicable if you are using a CA certificate from the Windows Trust Store (see [Use System Trust Store](#) on page 94).

- Enabled (1): The driver checks for certificate revocation while retrieving a certificate chain from the Windows Trust Store.
- Disabled (0): The driver does not check for certificate revocation while retrieving a certificate chain from the Windows Trust Store.

 **Note:**

This option is only available on Windows.

Convert Key Name to Lower Case

Key Name	Default Value	Required
LCaseSspKeyName	Selected (1)	No

Description

This option specifies whether the driver converts server-side property key names to all lower-case characters.

- Enabled (1): The driver converts server-side property key names to all lower-case characters.
- Disabled (0): The driver does not modify the server-side property key names.

Database

Key Name	Default Value	Required
Schema	default	No

Description

The name of the database schema to use when a schema is not explicitly specified in a query. You can still issue queries on other schemas by explicitly specifying the schema in the query.

 **Note:**

To inspect your databases and determine the appropriate schema to use, at the Impala command prompt, type `show databases`.

Default Keytab File

Key Name	Default Value	Required
DefaultKeytabFile	None	No

Description

The full path to the keytab file that the driver uses to obtain the ticket for Kerberos authentication.

Note:

- This option is applicable only when the authentication mechanism is set to Kerberos (`AuthMech=1`) and the Use Keytab option is enabled (`UseKeytab=1`).
- If the UPN Keytab Mapping File option (the `UPNKeytabMappingFile` key) is set to a JSON file with a valid mapping to a keytab, then that keytab takes precedence.

If you do not set this option but the Use Keytab option is enabled (`UseKeytab=1`), then the MIT Kerberos library will search for a keytab using the following search order:

- The file specified by the `KRB5_KTNAME` environment variable.
- The `default_keytab_name` setting in the `[libdefaults]` section of the Kerberos configuration file (`krb5.conf/krb5.ini`).
- The default keytab file specified in the MIT Kerberos library. Typically, the default file is `C:\Windows\krb5kt` for Windows platforms and `/etc/krb5.keytab` for non-Windows platforms.

Delegation UID

Key Name	Default Value	Required
DelegationUID	None	No

Description

If a value is specified for this setting, the driver delegates all operations against Impala to the specified user, rather than to the authenticated user for the connection.

Enable Auto Reconnect

Key Name	Default Value	Required
AutoReconnect	Selected (1)	Yes

Description

This option specifies whether the driver attempts to automatically reconnect to the server when a communication link error occurs.

- Enabled (1): The driver attempts to reconnect.
- Disabled (0): The driver does not attempt to reconnect.

Enable Query Retry

Key Name	Default Value	Required
EnableQueryRetry	Clear (0)	No

Description

This option specifies whether the driver automatically retries queries that are sent to the server but fail.

- Enabled (1): The driver retries failed queries.
- Disabled (0): The driver only submits each query once.

Query retry settings are configured through the following options:

- [Maximum Retries](#) on page 81
- [Result Set Cache Size](#) on page 85
- [Retry Interval](#) on page 85
- [GlobalResultSetCache](#) on page 97

Enable SSL

Key Name	Default Value	Required
SSL	Clear (0)	No

Description

This option specifies whether the client uses an SSL encrypted connection to communicate with the Impala.

- Enabled (1): The client communicates with the Impala using SSL.
- Disabled (0): SSL is disabled.

SSL is configured independently of authentication. When authentication and SSL are both enabled, the driver performs the specified authentication method over an SSL connection.

HTTP Path

Key Name	Default Value	Required
HTTPath	None	No

Description

The partial URL corresponding to the Impala server.

The driver forms the HTTP address to connect to by appending the HTTP Path value to the host and port specified in the DSN or connection string. For example, to connect to the HTTP address

`http://localhost:21050/gateway/sandbox/impala/version`, you would set HTTP Path to `/gateway/sandbox/impala/version`.

Host

Key Name	Default Value	Required
Host (or Server)	None	Yes

Description

The IP address or host name of the Impala server.

Host FQDN

Key Name	Default Value	Required
KrbFQDN	_HOST	No

Description

The fully qualified domain name of the Impala host.

When the value of Host FQDN is `_HOST`, the driver uses the Impala server host name as the fully qualified domain name for Kerberos authentication.

Ignore Transactions

Key Name	Default Value	Required
IgnoreTransactions	Clear (0)	No

Description

This option specifies whether the driver should simulate transactions, or return an error.

- Enabled (1): The driver simulates transactions, enabling queries that contain transaction statements to be run successfully. The transactions are not executed.
- Disabled (0): The driver returns an error if it attempts to run a query that contains transaction statements.



Note:

ODBC does not support transaction statements, so they cannot be executed.

Log Level

Key Name	Default Value	Required
LogLevel	OFF (0)	No

Description

Use this property to enable or disable logging in the driver and to specify the amount of detail included in log files.

! Important:

- Only enable logging long enough to capture an issue. Logging decreases performance and can consume a large quantity of disk space.
- The settings for logging apply to every connection that uses the Simba Impala ODBC Driver, so make sure to disable the feature after you are done using it.
- This option is not supported in connection strings. To configure logging for the Windows driver, you must use the Logging Options dialog box. To configure logging for a non-Windows driver, you must use the `simba.impalaodbc.ini` file.

Set the property to one of the following values:

- OFF (0): Disable all logging.
- FATAL (1): Logs severe error events that lead the driver to abort.
- ERROR (2): Logs error events that might allow the driver to continue running.
- WARNING (3): Logs events that might result in an error if action is not taken.
- INFO (4): Logs general information that describes the progress of the driver.
- DEBUG (5): Logs detailed information that is useful for debugging the driver.
- TRACE (6): Logs all driver activity.

When logging is enabled, the driver produces the following log files at the location you specify in the Log Path (`LogPath`) property:

- A `simbaimpalaodbcdriver.log` file that logs driver activity that is not specific to a connection.
- A `simbaimpalaodbcdriver_connection_[Number].log` file for each connection made to the database, where `[Number]` is a number that identifies each log file. This file logs driver activity that is specific to the connection.

If you enable the `UseLogPrefix` connection property, the driver prefixes the log file name with the user name associated with the connection and the process ID of the application through which the connection is made. For more information, see [UseLogPrefix](#) on page 101.

Log Path

Key Name	Default Value	Required
LogPath	None	Yes, if logging is enabled.

Description

The full path to the folder where the driver saves log files when logging is enabled.

! Important:

This option is not supported in connection strings. To configure logging for the Windows driver, you must use the Logging Options dialog box. To configure logging for a non-Windows driver, you must use the `simba.impalaodbc.ini` file.

Max File Size

Key Name	Default Value	Required
LogFileSize	20971520	No

Description

The maximum size of each log file in bytes. After the maximum file size is reached, the driver creates a new file and continues logging.

If this property is set using the Windows UI, the entered value is converted from megabytes (MB) to bytes before being set.

! Important:

This option is not supported in connection strings. To configure logging for the Windows driver, you must use the Logging Options dialog box. To configure logging for a non-Windows driver, you must use the `simba.impalaodbc.ini` file.

Max Number Files

Key Name	Default Value	Required
LogFileCount	50	No

Description

The maximum number of log files to keep. After the maximum number of log files is reached, each time an additional file is created, the driver deletes the oldest log file.

! Important:

This option is not supported in connection strings. To configure logging for the Windows driver, you must use the Logging Options dialog box. To configure logging for a non-Windows driver, you must use the `simba.impalaodbc.ini` file.

Maximum Retries

Key Name	Default Value	Required
MaxNumQueryRetries	5	No

Description

The maximum number of times that the driver retries a failed query, when query retry is enabled.

Also see [Enable Query Retry](#) on page 76.

Mechanism

Key Name	Default Value	Required
AuthMech	No Authentication (0)	No

Description

The authentication mechanism to use.

Select one of the following settings, or set the key to the corresponding number:

- No Authentication (0)
- Kerberos (1)
- SASL User Name (2)
- User Name And Password (3)

Minimum TLS

Key Name	Default Value	Required
Min_TLS	TLS 1.2 (1.2)	No

Description

The minimum version of TLS/SSL that the driver allows the data store to use for encrypting connections. For example, if TLS 1.1 is specified, TLS 1.0 cannot be used to encrypt connections.

- TLS 1.0 (1.0): The connection must use at least TLS 1.0.
- TLS 1.1 (1.1): The connection must use at least TLS 1.1.
- TLS 1.2 (1.2): The connection must use at least TLS 1.2.

Password

Key Name	Default Value	Required
PWD	None	Yes, if the authentication mechanism is User Name And Password (3).

Description

The password corresponding to the user name that you provided in the User Name field (the UID key).

Port

Key Name	Default Value	Required
Port	21050	Yes

Description

The number of the TCP port that the Impala server uses to listen for client connections.

Proxy Host

Key Name	Default Value	Required
ProxyHost	None	Yes, if connecting through a proxy server.

Description

The host name or IP address of a proxy server that you want to connect through.

Proxy Port

Key Name	Default Value	Required
ProxyPort	None	Yes, if connecting through a proxy server.

Description

The number of the port that the proxy server uses to listen for client connections.

Proxy Password

Key Name	Default Value	Required
ProxyPWD	None	Yes, if connecting to a proxy server that requires authentication.

Description

The password that you use to access the proxy server.

Proxy Username

Key Name	Default Value	Required
ProxyUID	None	Yes, if connecting to a proxy server that requires authentication.

Description

The user name that you use to access the proxy server.

Realm

Key Name	Default Value	Required
KrbRealm	NULL	No

Description

The realm of the Impala host.

If your Kerberos configuration already defines the realm of the Impala host as the default realm, then you do not need to configure this option.

Restrict Metadata with Current Schema

Key Name	Default Value	Required
CurrentSchema RestrictedMetadata	Clear (0)	No

Description

This option specifies whether the driver should restrict catalog function results to tables and views in the current schema if a catalog function call is made without specifying a schema, or if the schema is specified as the wildcard character %.

Note:

Restricting results to the tables and views in the current schema may improve the performance of catalog calls that do not specify a schema.

- Enabled (1): The driver restricts catalog function results to the current schema if a schema is not specified.
- Disabled (0): The driver does not restrict catalog function results to the current schema if a schema is not specified.

Result Set Cache Size

Key Name	Default Value	Required
ResultSetCacheSize	20MB	No

Description

The maximum amount of memory that the result set cache for the current connection can occupy. Values must be specified in: B (bytes), KB (kilobytes), MB (megabytes), or GB (gigabytes).

When query retries are enabled, the driver temporarily caches result sets. For more information about this feature, see [Enable Query Retry](#) on page 76.

For information about setting a maximum total cache size for all concurrent connections, see [GlobalResultSetCache](#) on page 97.

Retry Interval

Key Name	Default Value	Required
QueryRetryInterval	5S	No

Description

The amount of time that the driver waits between query retry attempts, when query retry is enabled. Values can be specified in S (seconds) or MS (milliseconds).

Also see [Enable Query Retry](#) on page 76.

Rows Fetched Per Block

Key Name	Default Value	Required
RowsFetchedPerBlock	10000	No

Description

The maximum number of rows that a query returns at a time.

Valid values for this setting include any positive 32-bit integer. However, testing has shown that performance gains are marginal beyond the default value of 10000 rows.

Save Password (Encrypted)

Key Name	Default Value	Required
N/A	Selected	No

Description

This option specifies whether the password is saved in the registry.

- Enabled: The password is saved in the registry.
- Disabled: The password is not saved in the registry.

This option is available only in the Windows driver. It appears in the Simba Impala ODBC Driver DSN Setup dialog box.

! Important:

The password is obscured (not saved in plain text). However, it is still possible for the encrypted password to be copied and used.

Service Name

Key Name	Default Value	Required
KrbServiceName	impala	No

Description

The Kerberos service principal name of the Impala server.

Socket Timeout

Key Name	Default Value	Required
SocketTimeout	30	No

Description

The number of seconds that the TCP socket waits for a response from the server before timing out the request and returning an error message.

When this option is set to 0, the TCP socket does not time out any requests.

String Column Length

Key Name	Default Value	Required
StringColumnLength	32767	No

Description

The maximum number of characters that can be contained in STRING columns.

Transport Buffer Size

Key Name	Default Value	Required
TSaslTransportBufSize	1000	No

Description

The number of bytes to reserve in memory for buffering unencrypted data from the network.

Note:

In most circumstances, the default value of 1000 bytes is optimal.

Transport Mode


Key Name	Default Value	Required
TransportMode	Binary (0) if using No Authentication, otherwise SASL (1).	No

Description

The transport protocol to use in the Thrift layer.

Select one of the following settings, or set the key to the number or string corresponding to the desired setting:

- Binary (0 or `binary`)
- SASL (1 or `sasl`)
- HTTP (2 or `http`)

 **Note:**

- If this property is specified, it takes precedence over the Use SASL property (`UseSASL`).
- If this property is not specified and the Use SASL property is specified, the Use SASL property takes precedence over the default value of this property.

For more information, see [Use Simple Authentication and Security Layer \(SASL\)](#) on page 93.

Trusted Certificates

Key Name	Default Value	Required
TrustedCerts	The <code>cacerts.pem</code> file in the <code>\lib</code> subfolder within the driver's installation directory. The exact file path varies depending on the version of the driver that is installed. For example, the path for the Windows driver is different from the path for the macOS driver.	No

Description

The full path of the `.pem` file containing trusted CA certificates, for verifying the server when using SSL.

If this option is not set, then the driver defaults to using the trusted CA certificates `.pem` file installed by the driver.

! Important:

If you are connecting from a Windows machine and the Use System Trust Store option is enabled, the driver uses the certificates from the Windows trust store instead of your specified `.pem` file. For more information, see [Use System Trust Store](#) on page 94.

UPN Keytab Mapping File

Key Name	Default Value	Required
UPNKeytabMappingFile	None	No

Description

The full path to a JSON file that maps your Impala user name to a Kerberos user principal name and a keytab file.

Note:

This option is applicable only when the authentication mechanism is set to Kerberos (`AuthMech=1`) and the Use Keytab option is enabled (`UseKeytab=1`).

The mapping in the JSON file must be written using the following schema, where `[UserName]` is the Impala user name, `[KerberosUPN]` is the Kerberos user principal name, and `[Keytab]` is the full path to the keytab file:

```
{
  "[UserName]": {
    "principal" : "[KerberosUPN]",
    "keytab" : "[Keytab]"
  },
  ... }
```

For example, the following file maps the Impala user name **simba** to the **simba@SIMBA** Kerberos user principal name and the `C:\Temp\simba.keytab` file:

```
{
  "simba": {
    "principal" : "simba@SIMBA",
    "keytab" : "C:\Temp\simba.keytab"
  },
  ... }
```

If parts of the mapping are invalid or not defined, then the following occurs:

- If the mapping file fails to specify a Kerberos user principal name, then the driver uses the Impala user name as the Kerberos user principal name.
- If the mapping file fails to specify a keytab file, then the driver uses the keytab file that is specified in the Default Keytab File setting.
- If the entire mapping file is invalid or not defined, then the driver does both of the actions described above.

Use Keytab

Key Name	Default Value	Required
UseKeytab	Clear (0)	No

Description

This option specifies whether the driver obtains the ticket for Kerberos authentication by using a keytab.

- Enabled (1): The driver uses a keytab to obtain a ticket before authenticating the connection using Kerberos.
- Disabled (0): The driver does not attempt to obtain the Kerberos ticket, and assumes that a valid ticket is already available in the credentials cache.



Note:

This option is applicable only when the authentication mechanism is set to Kerberos (`AuthMech=1`).

If you enable this option but do not set the Default Keytab File option (the `DefaultKeytabFile` key), then the MIT Kerberos library will search for a keytab file using the following search order:

1. The file specified by the `KRB5_KTNAME` environment variable.
2. The `default_keytab_name` setting in the `[libdefaults]` section of the Kerberos configuration file (`krb5.conf/krb5.ini`).
3. The default keytab file specified in the MIT Kerberos library. Typically, the default file is `C:\Windows\krb5kt` for Windows platforms.

Use Native Query

Key Name	Default Value	Required
<code>UseNativeQuery</code>	Clear (0)	No

Description

This option specifies whether the driver uses native Impala SQL queries, or converts the queries emitted by an application into an equivalent form in Impala SQL. If the application is Impala-aware and already emits Impala SQL, then enable this option to avoid the extra overhead of query transformation.

- Enabled (1): The driver does not transform the queries emitted by an application, and executes Impala SQL queries directly.
- Disabled (0): The driver transforms the queries emitted by an application and converts them into an equivalent form in Impala SQL.

! Important:

When this option is enabled, the driver cannot execute parameterized queries.

Use Only SSPI

Key Name	Default Value	Required
UseOnlySSPI	Clear (0)	No

Description

This option specifies how the driver handles Kerberos authentication: either with the SSPI plugin or with MIT Kerberos.

- **Enable For This DSN (1 in the DSN entry in the registry):** The driver handles Kerberos authentication in the DSN connection by using the SSPI plugin instead of MIT Kerberos by default.
- **Enable For DSN-less Connections (1 in the driver configuration section of the registry):** The driver handles Kerberos authentication in DSN-less connections by using the SSPI plugin instead of MIT Kerberos by default.

If you want all connections that use the Simba Impala ODBC Driver to use the SSPI plugin by default, then enable Use Only SSPI for both DSN and DSN-less connections.

- **Disabled (0):** The driver uses MIT Kerberos to handle Kerberos authentication, and only uses the SSPI plugin if the GSSAPI library is not available.

! Important:

This option is only available on Windows.

Use Proxy

Key Name	Default Value	Required
UseProxy	Clear (0)	No

Description

This option specifies whether the driver uses a proxy server to connect to the data store.

- Enabled (1): The driver connects to a proxy server based on the information provided in the Proxy Host, Proxy Port, Proxy Username, and Proxy Password fields or the `ProxyHost`, `ProxyPort`, `ProxyUID`, and `ProxyPWD` keys.
- Disabled (0): The driver connects directly to the Impala server.

Use Simple Authentication and Security Layer (SASL)

Key Name	Default Value	Required
UseSASL	0 if using No Authentication. 1 if using User Name And Password or Kerberos or SASL User Name authentication.	No

Description

This option specifies whether the driver uses SASL to handle authentication.

- Enabled (1): The driver uses SASL to handle authentication.
- Disabled (0): The driver does not use SASL.

This option is configurable only when you are using the User Name And Password authentication mechanism. If the driver is configured to use the other authentication mechanisms, then it uses the default setting for the Use Simple Authentication and Security Layer (SASL) option.

Note:

- If the Transport Mode property (`TransportMode`) is specified, it takes precedence over this property.
- If the Transport Mode property is not specified and this property is specified, this property takes precedence over the default value of Transport Mode.

For more information, see [Transport Mode](#) on page 88.

Use SQL Unicode Types

Key Name	Default Value	Required
UseSQLUnicodeTypes	Clear (0)	No

Description

This option specifies the SQL types to be returned for string data types.

- Enabled (1): The driver returns SQL_WVARCHAR for STRING and VARCHAR columns, and returns SQL_WCHAR for CHAR columns.
- Disabled (0): The driver returns SQL_VARCHAR for STRING and VARCHAR columns, and returns SQL_CHAR for CHAR columns.

Use System Trust Store

Key Name	Default Value	Required
UseSystemTrustStore	Clear (0)	No

Description

This option specifies whether to use a CA certificate from the system trust store, or from a specified `.pem` file.

- Enabled (1): The driver verifies the connection using a certificate in the system trust store.
- Disabled (0): The driver verifies the connection using a specified `.pem` file. For information about specifying a `.pem` file, see [Trusted Certificates](#) on page 89.

! Important:

If you are connecting from a Windows machine and you want to specify a `.pem` file containing trusted CA certificates, this option must be disabled. For more information, see [Trusted Certificates](#) on page 89.

Note:

This option is only available on Windows.

User Name

Key Name	Default Value	Required
UID	For User Name (2) authentication only, the default value is anonymous	Yes, if the authentication mechanism is User Name And Password (3). No, if the authentication mechanism is SASL User Name (2).

Description

The user name that you use to access the Impala server.

Configuration Options Having Only Key Names

The following configuration options do not appear in the Windows user interface for the Simba Impala ODBC Driver. They are accessible only when you use a connection string, configure driver-wide settings, or configure a connection from a Linux/macOS/AIX/Solaris machine:

- [DelegationUserIDCase](#) on page 96
- [DisableOptimizedEncodingConverter](#) on page 96
- [Driver](#) on page 97
- [GlobalResultSetCache](#) on page 97
- [HTTPAuthCookies](#) on page 98
- [http.header.](#) on page 98
- [MaxCatalogNameLen](#) on page 99
- [MaxColumnNameLen](#) on page 99
- [MaxSchemaNameLen](#) on page 99
- [MaxTableNameLen](#) on page 100
- [SSP_](#) on page 100

The `UseLogPrefix` property must be configured as a Windows Registry key value, or as a driver-wide property in the `simba.impalaodbc.ini` file for macOS or Linux.

- [UseLogPrefix](#) on page 101

DelegationUserIDCase

Key Name	Default Value	Required
DelegationUserIDCase	Unchanged	No

Description

This option specifies whether the driver changes the Delegation UID (or `DelegationUID`) value to all upper-case or all lower-case. The following values are supported:

- `Upper`: Change the delegated user name to all upper-case.
- `Lower`: Change the delegated user name to all lower-case.
- `Unchanged`: Do not modify the delegated user name.

For more information about delegating a user name, see [Delegation UID](#) on page 75.

DisableOptimizedEncodingConverter

Key Name	Default Value	Required
DisableOptimizedEncodingConverter	false	No

Description

This driver-wide option controls which data encoding converter the driver uses.

Note:

Enabling this option may result in decreased performance.

- `true`: The driver uses a standard ICU converter.
- `false`: The driver uses an optimized converter.

Important:

This option applies to every connection that uses the Simba Impala ODBC Driver. For more information, see [Setting Driver-Wide Configuration Options on Windows](#) on page 24 or [Setting Driver-Wide Configuration Options on a Non-Windows Machine](#) on page 57.

Driver

Key Name	Default Value	Required
Driver	Simba Impala ODBC Driver when installed on Windows, or the absolute path of the driver shared object file when installed on a non-Windows machine.	Yes

Description

On Windows, the name of the installed driver (Simba Impala ODBC Driver).

On other platforms, the name of the installed driver as specified in `odbcinst.ini`, or the absolute path of the driver shared object file.

GlobalResultSetCache

Key Name	Default Value	Required
GlobalResultSetCache	200MB	No

Description

The maximum total amount of memory that can be occupied by result set caches across concurrent connections. Values must be specified in: B (bytes), KB (kilobytes), MB (megabytes), or GB (gigabytes).

For example, when this property is set to the default value of 200MB, if you have 3 concurrent Impala connections, the total amount of memory consumed by the 3 result set caches for those connections cannot exceed 200MB.

These result set caches are used only when query retries are enabled. For more information about this feature, see [Enable Query Retry](#) on page 76.

For information about setting a maximum cache size for the current connection only, see [Result Set Cache Size](#) on page 85.

HTTPAuthCookies

Key Name	Default Value	Required
HTTPAuthCookies	None	No

Description

A comma-separated list of authentication cookies that are supported by the driver.

If cookie-based authentication is enabled in your server, the driver authenticates the connection once based on the provided authentication credentials. It then uses the cookie generated by the server for each subsequent request in the same connection.

http.header.

Key Name	Default Value	Required
http.header.	None	No

Description

Set a custom HTTP header by using the following syntax, where *[HeaderKey]* is the name of the header to set and *[HeaderValue]* is the value to assign to the header:

```
http.header.[HeaderKey]=[HeaderValue]
```

For example:

```
http.header.AUTHENTICATED_USER=john
```

After the driver applies the header, the http.header. prefix is removed from the DSN entry, leaving an entry of *[HeaderKey]=[HeaderValue]*

The example above would create the following custom HTTP header:

```
AUTHENTICATED_USER: john
```

Note:

- The `http.header.` prefix is case-sensitive.
- This option is applicable only when you are using HTTP as the Thrift transport protocol. For more information, see [Transport Mode](#) on page 88.

MaxCatalogNameLen

Key Name	Default Value	Required
MaxCatalogNameLen	0	No

Description

The maximum number of characters that can be returned for catalog names.

This option can be set to any integer from 0 to 65535, inclusive. To indicate that there is no maximum length or that the length is unknown, set this option to 0.

MaxColumnNameLen

Key Name	Default Value	Required
MaxColumnNameLen	0	No

Description

The maximum number of characters that can be returned for column names.

This option can be set to any integer from 0 to 65535, inclusive. To indicate that there is no maximum length or that the length is unknown, set this option to 0.

MaxSchemaNameLen

Key Name	Default Value	Required
MaxSchemaNameLen	256	No

Description

The maximum number of characters that can be returned for schema names.

This option can be set to any integer from 0 to 65535, inclusive. To indicate that there is no maximum length or that the length is unknown, set this option to 0.

MaxTableNameLen

Key Name	Default Value	Required
MaxTableNameLen	0	No

Description

The maximum number of characters that can be returned for table names.

This option can be set to any integer from 0 to 65535, inclusive. To indicate that there is no maximum length or that the length is unknown, set this option to 0.

SSP_

Key Name	Default Value	Required
SSP_	None	No

Description

Set a server-side property by using the following syntax, where *[SSPKey]* is the name of the server-side property and *[SSPValue]* is the value for that property:

```
SSP_[SSPKey]=[SSPValue]
```

For example:

```
SSP_MEM_LIMIT=1000000000
SSP_REQUEST_POOL=myPool
```

Or, to set those properties in a connection string, type the following:

```
SSP_MEM_LIMIT={1000000000};SSP_REQUEST_POOL={myPool}
```

After the driver applies the server-side property, the `SSP_` prefix is removed from the DSN entry, leaving an entry of *[SSPKey]=[SSPValue]*.

! Important:

This property is supported only for connections to Impala 2.0 or later. In earlier versions of Impala, the SET statement can only be executed from within the Impala shell.

Note:

- The `SSP_` prefix must be upper case.
- When setting a server-side property in a connection string, it is recommended that you enclose the value in braces (`{ }`) to make sure that special characters can be properly escaped.

UseLogPrefix

Key Name	Default Value	Required
UseLogPrefix	0	No

Description

This option specifies whether the driver includes a prefix in the names of log files so that the files can be distinguished by user and application.

Set the property to one of the following values:

- 1: The driver prefixes log file names with the user name and process ID associated with the connection that is being logged.

For example, if you are connecting as a user named "jdoe" and using the driver in an application with process ID 7836, the generated log files would be named `jdoe_7836_simbaimpalaodbcdriver.log` and `jdoe_7836_simbaimpalaodbcdriver_connection_[Number].log`, where *[Number]* is a number that identifies each connection-specific log file.

- 0: The driver does not include the prefix in log file names.

To configure this option for the Windows driver, you create a value for it in one of the following registry keys:

- For a 32-bit driver installed on a 64-bit machine: `HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Simba\Simba Impala ODBC Driver\Driver`
- Otherwise: `HKEY_LOCAL_MACHINE\SOFTWARE\Simba\Simba Impala ODBC Driver\Driver`

Use `UseLogPrefix` as the value name, and either 0 or 1 as the value data.

To configure this option for a non-Windows driver, you must use the `simba.impalaodbc.ini` file.

Third-Party Trademarks

IBM and AIX are trademarks or registered trademarks of IBM Corporation or its subsidiaries in Canada, United States, and/or other countries.

Kerberos is a trademark of the Massachusetts Institute of Technology (MIT).

Linux is the registered trademark of Linus Torvalds in Canada, United States and/or other countries.

Mac, macOS, Mac OS, and OS X are trademarks or registered trademarks of Apple, Inc. or its subsidiaries in Canada, United States and/or other countries.

Microsoft, MSDN, Windows, Windows Azure, Windows Server, Windows Vista, and the Windows start button are trademarks or registered trademarks of Microsoft Corporation or its subsidiaries in Canada, United States and/or other countries.

Red Hat, Red Hat Enterprise Linux, and CentOS are trademarks or registered trademarks of Red Hat, Inc. or its subsidiaries in Canada, United States and/or other countries.

Solaris is a registered trademark of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

SUSE is a trademark or registered trademark of SUSE LLC or its subsidiaries in Canada, United States and/or other countries.

Apache Impala, Apache, and Impala are either registered trademarks or trademarks of The Apache Software Foundation in the United States and other countries.

All other trademarks are trademarks of their respective owners.